ManageEngine ADSelfService Plus

# Establishing a secure connection between ADSelfService Plus and MS SQL



# **Table of Contents**

Document summary ————————————————————————————————————	1
Prerequisites ————————————————————————————————————	1
Step 1: Importing the certificate to the certificate store	2
Step 2: Associating the certificate with the MS SQL Server	5
Step 3: Configuring ADSelfService Plus	7
Step 4: Associating the certificate to Java key store	8
Appendix	10
SSL encryption for failover clustering in SQL Server	10
Creating self-signed certificate using IIS	10
Checking for SSL certificate validity	11



## **Document summary**

ADSelfService Plus supports the external MS SQL database in addition to the bundled PostgreSQL database. This document is intended for admins who want to secure the connection between their MS SQL database and ADSelfService Plus with an SSL certificate. By applying an SSL certificate in the SQL server, you can ensure that the data transferred between ADSelfService Plus and the SQL server is encrypted and stays secure during transmission.

# **Prerequisites**

- You'll need a valid SSL certificate in PFX format that isn't expiring soon. If you have a certificate in another format, please convert it into a PFX file. To create a self-signed certificate using IIS, follow the steps mentioned here.
- The Common Name in the Subject field of the certificate must be the same as the fully qualified domain name (FQDN) of the machine in which the MS SQL Server is installed.
- The certificate must be issued for server authentication, so the Enhanced Key Usage property of the certificate should include "Server Authentication (1.3.6.1.5.5.7.3.1)."

Steps to check whether your certificate meets these requirements are listed here.

**Important:** If you've already applied a valid SSL certificate (matching the requirements in prerequisites) in your SQL Server, you can start on Step 3.


## STEP 1 Importing the certificate to the certificate store

If you're using a self-signed SSL certificate generated using Internet Information Services (IIS) Manager, you can start on Step 2.


If you're using a certificate generated through other modes, then you must first import it to the certificate store in SQL Server. You can import the certificate using either IIS Manager or the Microsoft Management Console (MMC) snap-in.

#### Importing the certificate using IIS Manager

- 1. Open IIS Manager.
- 2. Click on the name of the server in the **Connections** column in the left pane. In the middle row of icons, double-click on **Server Certificates**.



3. Click Import in the Actions pane.




- 4. Browse and select the PFX certificate file.
- 5. Enter the password that you used while generating the certificate file.




6. Click OK.

#### Importing the certificate using MMC


- 1. Open MMC.
- 2. From the File menu, click Add or Remove Snap-in...
- 3. Select Certificates, and click Add.




- 4. You'll be prompted to open the snap-in for your user account, the service account, or the computer account. Select the **Computer Account**.
- 5. Select Local computer, and then click Finish.



- 6. Click **OK** to exit Add or Remove Snap-in.
- 7. Back in the MMC, double-click Certificates (Local Computer) to expand the tree view.
- 8. Right-click on Personal, and select All Tasks > Request New Certificate...




- 9. Click **Next** in the Certificate Request Wizard that opens.
- 10. Select **Computer** as the certificate type.




11. You can either enter a name in text box or leave it blank. Then complete the wizard by clicking **Enroll** and then clicking **Finish**.

### STEP 2 Associating the certificate with MS SQL Server


- 1. Open SQL Server Configuration Manager.
- 2. Expand **SQL Server Network Configuration** and right-click on **Protocols** for the MS SQL Server instance to which you want to associate the certificate. Then click **Properties.**



3. On the Flags tab, select **Yes** in the Force Encryption box.



4. On the Certificate tab, select the certificate you want to use.



- 5. Click OK.
- 6. Restart SQL Server.

## STEP 3 Configuring ADSelfService Plus

After associating the certificate with SQL Server, you need to configure ADSelfService Plus to use the secure connection to the database. Follow the steps below:

1. Go to the **conf** folder in the ADSelfService Plus installation directory (By default: C:\Program Files\ ManageEngine\ADSelfService Plus\conf) and open the **database\_params.conf** file in a text editor.

- 2. You'll see a list of entries such as login, password, and url.
- 3. Under the URL entry, append ssl=authenticate to the URL value.

For example, if the existing entry is:

url=jdbc:jtds:sqlserver://WIN-K1HC49RFJU4:49958;DatabaseName=SQL\_SSL;Domain=WIN-K1HC49RFJU4:useNTLMv2=true

Then change it to:

url=jdbc:jtds:sqlserver://WIN-K1HC49RFJU4:49958;DatabaseName=SQL\_SSL;Domain=WIN-K1HC49RFJU4;useNTLMv2=true;*ssl=authenticate* 

```
🔚 database_params.conf 🗵
       transaction_isolation = TRANSACTION_READ_COMMITTED
       sglgenerator = com.adventnet.db.adapter.mssgl.MssglSOLGenerator
       url = jdbc:jtds:gglserver://WIN-K1HC49RFJU4:49958;DatabaseName=SQL_SSL;Domain=WIN-K1HC49RFJU4;useNTLMv2=true;ssl=authenticate
      dbadapter = com.adventnet.db.adapter.mssql.MssqlDBAdapter
      exceptionsorterclassname = com.adventnet.db.adapter.mssql.MssqlExceptionSorter
      username = Administrator
      maxsize = 20
      drivername = net.sourceforge.jtds.jdbc.Driver
      minsize = 1
      password = 8c7fcc8eca0037f8b48df8606c75a866
                                     lenath: 518 lines: 11
Normal text file
                                                                  Ln:3 Col: 126 Sel: 010
                                                                                                        Unix (LF)
                                                                                                                        UTF-8
                                                                                                                                          INS
```

- 4. In the same **conf** folder, open **wrapper.conf** in a text editor.
- 5. Search for wrapper.java.additional. You'll get a list of entries that are numbered starting at 1.
- 6. Add the below line after the last wrapper.java.additional entry.

"wrapper.java.additional.xx=-Djsse.enableCBCProtection=false"

Where 'xx' denotes the next value to the preceding line's integer.

For example,

wrapper.java.additional.1=-Dcatalina.home=..

wrapper.java.additional.2=-Dserver.home=..

wrapper.java.additional.3=-Dserver.stats=1000

•••

wrapper.java.additional.12=-DSSL PORT=8443

wrapper.java.additional.13=-Djsse.enableCBCProtection=false

```
wrapper.java.additional.4=-Djava.util.logging.manager=org.apache.juli.ClassLoaderLogManager
      wrapper.java.additional.5=-Djava.util.logging.config.file=../conf/logging.properties
      wrapper.java.additional.6=-Duser.home=../logs
      wrapper.java.additional.7=-Dlog.dir=../logs
      wrapper.java.additional.8=-Ddb.home=../pgsql
      wrapper.java.additional.9=-Dcheck.tomcatport="true"
      wrapper.java.additional.10=-Dproduct.home=..
      wrapper.java.additional.ll=-DHTTP_PORT=8888
      wrapper.java.additional.12=-DSSL_PORT=9251
      wrapper.java.additional.13=-Dfile.encoding=UTF-8
      wrapper.java.additional.14=-Djava.io.tmpdir=../temp
      #The below line will be executed, when out of memory error occurs.
      wrapper.java.additional.15=-XX:OnOutOfMemoryError="SetMaxMemory.bat"
                                                                               #Call SetMaxMemory.bat file
      wrapper.java.additional.16=-Dhaltjvm.on.dbcrash="true"
      wrapper.java.additional.17=-Dorg.apache.catalina.SESSION_COOKIE_NAME=JSESSIONIDADSSP
      wrapper.java.additional.18=-Dhttps.protocols=TLSv1.2,TLSv1,TLSv1.1
      wrapper.java.additional.19=-XX:-CreateMinidumpOnCrash
  63
      wrapper.java.additional.20=-Djsse.enableCBCProtection=false
  64
      wrapper.java.additional.21=-Djdk.tls.client.protocols=TLSv1.2,TLSv1,TLSv1.1
  65
      wrapper.java.additional.22=-Djsse.enableCBCProtection=false
  66
  67
      #This filter trigger action will restart the jvm on out of memory error.
 68
      wrapper.filter.trigger.l=java.lang.OutOfMemoryError
      wrapper.filter.action.l=RESTART
  69
  70
      wrapper.filter.message.l=The JVM has run out of memory.
      #uncomment the following to enable JPDA debugging
       #wrapper.java.additional.3=-Xdebug
      #wrapper.java.additional.4=-Xnoagent
       Armonnon ious additional E- Vmunidemetranonant-dt acabat
Normal te length: 6,067 lines: 152
                                    Ln:65 Col:27 Sel:0|0
                                                                                          UTF-8
```


7. Restart ADSelfService Plus to finish.

#### STEP 4 Associating the certificate to Java Key Store

You need to associate the certificate with the ADSelfService Plus Java KeyStore to establish trust.

Follow the steps given below in the machine in which ADSelfService Plus is installed:

- 1. Open IIS Manager.
- 2. In the middle pane, click Server Certificates.
- 3. Open the certificate that you want to use.
- 4. Click on the **Details** tab.
- 5. Click Copy to file.
- 6. Click Next in the Certificate Export Wizard that opens.
- 7. In the Export Private Key screen, select No, do not export the private key, and click Next.



8. In the Export File Format screen, select either DER encoded binary X.509 (.CER) or Base-64 encoded X.509 (.CER), and click Next.



- 9. Enter a name for the file, and click Next.
- 10. Click Finish.
- 11. Go the the **jre** folder in the ADSelfService Plus installation directory (By default: C:\Program Files\ ManageEngine\ADSelfService Plus\jre). Open the **bin** folder.
- 12. Open Command Prompt and run the following command:

"%ADSelfService\_Plus\_Installation\_directory\jre\bin\keytool" -import-v-trustcacerts -alias myserver -file ssl.cer -keystore

"%ADSelfService\_Plus\_Installation\_directory\jre\lib\security\cacerts" -keypass changeit -storepass changeit -noprompt

Where "%ADSelfService\_Plus\_Installation\_directory\jre\bin\keytool" specifies the location of the keytool.exe utility, which is used to manage keys and certificates.

Replace this path with the ADSelfService Plus installation directory, which by default is: *C:\Program Files\ManageEngine\ADSelfService Plus\jre\bin.* 

# **Appendix**

#### SSL encryption for failover clustering in SQL Server

If you'd like to use encrypted connections in a clustered environment, then you should have a certificate issued to the fully qualified DNS name of the failover clustered instance. Also, this certificate should be installed on all of the nodes in the failover cluster. Additionally, you'll have to edit the thumbprint of the certificate in the registry because it's set to Null in a clustered environment

The following steps should be performed on all of the nodes in the cluster:

- 1. Open the certificate using the MMC Certificates Snap-in.
- 2. Copy the hex value from the Thumbprint property on the Details tab to Notepad and remove the spaces.
- 3. Start **regedit** and copy the **hex value** to this key: HKLM\SOFTWARE\Microsoft\Microsoft SQL Server\< YourSQLServerInstance>\MSSQLServer\SuperSocketNetLib\Certificate.
- 4. You'll now have to reboot your node, so it's recommended that you failover to another node first.
- 5. Repeat this procedure on all nodes.

#### Creating self-signed certificates using IIS

- 1. Open IIS Manager.
- 2. Click on the **server name** in the *Connections* column in the left pane.
- 3. Double-click on Server Certificates in the middle pane.
- 4. Click on Create Self-Signed Certificate in the Actions column on the right.
- 5. Enter a name, and click **OK** to proceed.
- 6. Click OK.

You should now see the SSL certificate valid for one year.

#### Checking for SSL certificate validity

- 1. Open MMC.
- 2. On the File menu, click Add or Remove Snap-in...
- 3. Select Certificates and click Add.
- 4. You'll be prompted to open the snap-in for your user account, the service account, or the computer account. Select the **Computer Account**.
- 5. Select Local computer, and then click Finish.
- 6. Click **OK** to exit Add or Remove Snap-in.
- 7. Back in the MMC, open the **Certificates** snap-in.
- 8. Double-click on Personal and then Certificates.
- 9. In the right pane, locate the certificate you're going to use.
- 10. The value for the *Intended Purpose* column must be **Server Authentication**.
- 11. The value for the *Issued* To column must be the **server name**.
- 12. Now, double-click the **certificate** to view its properties.
- 13. Under the *General* tab, you should be able to view the message "You have a private key that corresponds to this certificate."
- 14. Under the *Details* tab, the value of the *Subject* field must be the **server name**.
- 15. The value for the Enhanced Key Usage field must be Server Authentication (1.3.6.1.5.5.7.3.1).
- 16. Under the Certificate Path tab, the server name must appear under the certification path.

#### **Our Products**

AD360 | Log360 | ADManager Plus | ADAudit Plus | RecoveryManager Plus | M365 Manager Plus

# ManageEngine ADSelfService Plus

ADSelfService Plus is an identity security solution to ensure secure and seamless access to enterprise resources and establish a Zero Trust environment. With capabilities such as adaptive multi-factor authentication, single sign-on, self-service password management, a password policy enhancer, remote work enablement and workforce self-service, ADSelfService Plus provides your employees with secure, simple access to the resources they need. ADSelfService Plus helps keep identity-based threats out, fasttracks application onboarding, improves password security, reduces help desk tickets and empowers remote workforces. For more information about ADSelfService Plus, visit www.manageengine.com/products/self-service-password.