

Elastic IP

User Guide

Issue 01
Date 2024-12-11



Copyright © Huawei Technologies Co., Ltd. 2024. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Technologies Co., Ltd.

Trademarks and Permissions



HUAWEI and other Huawei trademarks are trademarks of Huawei Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Huawei Technologies Co., Ltd.

Address: Huawei Industrial Base
Bantian, Longgang
Shenzhen 518129
People's Republic of China

Website: <https://www.huawei.com>

Email: support@huawei.com

Security Declaration

Vulnerability

Huawei's regulations on product vulnerability management are subject to the *Vul. Response Process*. For details about this process, visit the following web page:

<https://www.huawei.com/en/psirt/vul-response-process>

For vulnerability information, enterprise customers can visit the following web page:

<https://securitybulletin.huawei.com/enterprise/en/security-advisory>

Contents

1 Permissions Management.....	1
1.1 Creating a User and Granting EIP Permissions.....	1
1.2 EIP Custom Policies.....	2
2 Elastic IP.....	4
2.1 EIP Overview.....	4
2.2 Assigning an EIP.....	6
2.3 Binding an EIP to an Instance.....	12
2.4 Unbinding an EIP from an Instance.....	13
2.5 Releasing or Unsubscribing an EIP.....	14
2.6 Changing Dedicated Bandwidth Size of an EIP.....	15
2.7 Modifying an EIP Bandwidth.....	18
2.8 Exporting EIP Information.....	20
2.9 Managing EIP Tags.....	21
2.10 IPv6 EIP.....	22
2.10.1 IPv6 EIP Overview.....	22
2.10.2 Assigning or Releasing an IPv6 EIP.....	28
3 EIP Billing.....	30
3.1 Changing EIP Billing Mode.....	30
3.2 Renewing a Yearly/Monthly EIP.....	33
3.3 Viewing the EIP Billing Information.....	34
4 EIP Pool.....	35
4.1 EIP Pool Overview.....	35
4.2 Purchasing an EIP Pool.....	35
4.3 Modifying an EIP Pool.....	37
4.4 Unsubscribing from an EIP Pool.....	38
4.5 Renewing an EIP Pool.....	38
5 Shared Bandwidth.....	39
5.1 Shared Bandwidth Overview.....	39
5.2 Assigning a Shared Bandwidth.....	40
5.3 Adding EIPs to a Shared Bandwidth.....	42
5.4 Removing EIPs from a Shared Bandwidth.....	43
5.5 Modifying a Shared Bandwidth.....	43

5.6 Deleting a Shared Bandwidth.....	45
5.7 Exporting Shared Bandwidths.....	45
6 Shared Data Package.....	46
6.1 Shared Data Package Overview.....	46
6.2 Buying a Shared Data Package.....	47
6.3 Viewing the Usage Details and Configuring Remaining Usage Alerts.....	48
7 Global EIPs.....	50
7.1 Global EIP Overview.....	50
7.2 Assigning a Global EIP.....	53
7.3 Binding a Global EIP to an Instance.....	56
7.4 Unbinding a Global EIP from an Instance.....	57
7.5 Viewing Details About a Global EIP.....	58
7.6 Releasing a Global EIP.....	58
7.7 Modifying the Global Connection Bandwidth of a Global EIP.....	59
7.8 Modifying the Global Internet Bandwidth of a Global EIP.....	59
8 Global Internet Gateways.....	61
8.1 Global Internet Gateway Overview.....	61
8.2 Creating a Global Internet Gateway.....	62
8.3 Deleting a Global Internet Gateway.....	64
8.4 Modifying a Global Internet Gateway.....	64
8.5 Binding a Global Internet Gateway to a Global EIP.....	65
8.6 Unbinding a Global Internet Gateway from a Global EIP.....	65
9 Global Internet Bandwidths.....	67
9.1 Overview.....	67
9.2 Buying a Global Internet Bandwidth.....	68
9.3 Adding Global EIPs to a Global Internet Bandwidth.....	71
9.4 Modifying a Global Internet Bandwidth.....	71
9.5 Viewing a Global Internet Bandwidth.....	72
9.6 Deleting a Global Internet Bandwidth.....	72
10 Global Connection Bandwidths.....	74
10.1 Overview.....	74
10.2 Buying a Global Connection Bandwidth.....	78
10.3 Adding Instances to a Global Connection Bandwidth.....	81
10.4 Removing Instances from a Global Connection Bandwidth.....	82
10.5 Managing a Global Connection Bandwidth.....	83
11 Cloud Eye Monitoring.....	84
11.1 Supported Metrics.....	84
11.2 Viewing Metrics.....	86
11.3 Creating an Alarm Rule.....	87

11.4 Exporting Monitoring Data..... 87

1 Permissions Management

1.1 Creating a User and Granting EIP Permissions

Currently, the EIP service permissions are included in the VPC permissions. [Permissions Management](#)

This section describes how to use IAM to implement fine-grained permissions control for your VPC resources. With IAM, you can:

- Create IAM users for personnel based on your enterprise's organizational structure. Each IAM user has their own identity credentials for accessing VPC resources.
- Grant users only the permissions required to perform a given task based on their job responsibilities.
- Entrust a HUAWEI ID or cloud service to perform efficient O&M on your VPC resources.

If your HUAWEI ID meets your permissions requirements, you can skip this section.

[Figure 1-1](#) shows the process flow for granting permissions.


Prerequisites

Before granting permissions to user groups, learn about [EIP Permissions](#) for EIP.

To grant permissions for other services, learn about all [system-defined permissions](#) supported by IAM.

Process Flow

Figure 1-1 Process for granting EIP permissions



1. On the IAM console, **create a user group and grant it permissions**.
Create a user group on the IAM console and assign the **EIP ReadOnlyAccess** permissions to the group.
2. **Create an IAM user and add it to the created user group**.
Create a user on the IAM console and add the user to the group created in 1.
3. **Log in as the IAM user** and verify permissions.
In the authorized region, perform the following operations:
 - Choose **Service List > Elastic IP**. Then click **Buy EIP** on the EIP console. If a message appears indicating that you have insufficient permissions to perform the operation, the **EIP ReadOnlyAccess** policy is in effect.
 - Choose another service from **Service List**. If a message appears indicating that you have insufficient permissions to access the service, the **EIP ReadOnlyAccess** policy is in effect.

1.2 EIP Custom Policies

Custom policies can be created as a supplement to the system policies of EIP. For the actions supported for custom policies, see [Permissions Policies and Supported Actions](#).

You can create custom policies in either of the following ways:

- Visual editor: Select cloud services, actions, resources, and request conditions. This does not require knowledge of policy syntax.
- JSON: Edit JSON policies from scratch or based on an existing policy.

For details, see [Creating a Custom Policy](#). The following section contains examples of common EIP custom policies.

Example Custom Policies

- Example 1: Grant permissions to assign and view EIPs

```
{
  "Version": "1.1",
  "Statement": [
    {
      "Effect": "Allow",
      "Action": [
        "vpc:publicips:create",
        "vpc:publicips:list"
      ]
    }
  ]
}
```

- Example 2: Grant permission to deny EIP deletion.

A policy with only "Deny" permissions must be used together with other policies. If the permissions granted to an IAM user contain both "Allow" and "Deny", the "Deny" permissions take precedence over the "Allow" permissions.

Assume that you want to grant the permissions of the **EIP FullAccess** policy to a user but want to prevent them from releasing EIPs. You can create a custom policy for denying EIP release, and attach both policies to the user. As an explicit deny in any policy overrides any allows, the user can perform all operations on EIPs except releasing them. Example policy denying EIP release:

```
{
  "Version": "1.1",
  "Statement": [
    {
      "Effect": "Deny",
      "Action": [
        "vpc:publicips:delete"
      ]
    }
  ]
}
```

- Example 3: Create a custom policy containing multiple actions.

A custom policy can contain the actions of one or multiple services that are of the same type (global or project-level). Example policy containing multiple actions:

```
{
  "Version": "1.1",
  "Statement": [
    {
      "Effect": "Allow",
      "Action": [
        "vpc:publicips:update",
        "vpc:publicips:create"
      ]
    },
    {
      "Effect": "Deny",
      "Action": [
        "vpc:publicips:delete"
      ]
    }
  ]
}
```

2 Elastic IP

2.1 EIP Overview


EIP

The Elastic IP (EIP) service enables your cloud resources to communicate with the Internet using static public IP addresses and scalable bandwidths. If a resource has an EIP bound, it can directly access the Internet. If a resource only has a private IP address, it cannot directly access the Internet.

EIPs can be bound to or unbound from ECSs, BMSs, virtual IP addresses, NAT gateways, or load balancers.

Each EIP can be bound to only one cloud resource and they must be in the same region.

Figure 2-1 Connecting to the Internet using an EIP



EIP Quotas

You can log in to the console to query your EIP quotas.

If you want to increase your quota, see [How Do I Apply for a Higher Quota?](#)

- Your request for a larger quota will only be approved if your account has valid orders and you are continuously using cloud resources. If you have released resources immediately after subscribing to them multiple times, your request for quota increase will be declined.
- If you have increased the EIP quota but you have not used the quota for a long time, Huawei Cloud will reduce the quota to the default value.

EIP Advantages

- Flexibility
EIPs can be flexibly bound to or unbound from ECSs, BMSs, NAT gateways, load balancers, or virtual IP addresses. The bandwidth can be scaled according to service changes.
- Flexible billing
EIPs are available on a pay-per-use (bandwidth usage or amount of traffic is billed) basis. The yearly/monthly billing mode is more preferential.
- Shared bandwidth
EIPs can use shared bandwidth to lower bandwidth costs.
- Immediate use
EIP binding, unbinding, and bandwidth adjustments take effect immediately.

Notes and Constraints

- If a yearly/monthly EIP is not renewed after it expires, or if the arrears of a pay-per-use EIP are not paid in time, the EIP may be released and cannot be recovered.
- An EIP and its bound cloud resource can use different billing modes.
For example, a yearly/monthly EIP can be bound to a pay-per-use ECS.
- If the used EIP bandwidth exceeds the purchased size or is attacked (usually by a DDoS attack), the EIP will be blocked but can still be bound or unbound.
- EIPs cannot be transferred across accounts, which means the EIP of an account cannot be transferred to another account.
- An EIP can be bound to only one cloud resource, and the EIP and the resource must be in the same region.
- The EIP remains unchanged:
 - No matter you start or stop the ECS.
 - When you modify its billing mode or supported bandwidth.

2.2 Assigning an EIP

Scenarios

You can assign an EIP and bind it to cloud resources to allow them to access the Internet.

NOTE


If you want to assign a pay-per-use EIP that you have released or assign a specific pay-per-use EIP, you can use APIs. When assigning an EIP, set the value of `ip_address` to the IP address that you want to assign. For details, see [Elastic IP API Reference](#).

- If the EIP has been assigned to another user, you will fail to assign your required EIP.
- You cannot use APIs to assign a yearly/monthly EIP that you have released or assign a specific yearly/monthly EIP.
- The management console does not support assigning a specific EIP.

Procedure

1. Go to the [Buy EIP](#) page.
2. Set the parameters as prompted.

Figure 2-2 Assigning an EIP



< | Buy EIP Assured Purchase Flexible Billing Docume

Basic Configuration

Billing Mode: Yearly/Monthly Pay-per-use

Region:

Regions are geographic areas isolated from each other. For low network latency and quick resource access, select the region nearest to where your services will be accessed.

EIP Type

EIP Type: Dynamic BGP Static BGP ?

Greater than or equal to 99.95% service availability rate

Bandwidth (Mbit/s): 1 2 5 10 100 200 Custom The value ranges from 1 to 2000 Mbit/s. ?

Bandwidth Name:

DDoS Protection

DDoS Protection: Cloud Native Anti-DDoS Basic Provides up to 5 Gbit/s of DDoS mitigation capacity for free. If the attack to an EIP exceeds 5 Gbit/s, the EIP will be blocked. ?

EIP Details

EIP Name:

Enterprise Project: ? [Create Enterprise Project](#)

EIP Reservation Price: + Bandwidth Price:

You will be charged based on the bill. [Pricing details](#) Next

Table 2-1 Parameter descriptions

Parameter	Description	Example Value
Billing Mode	The following billing modes are available: <ul style="list-style-type: none">• Yearly/Monthly• Pay-per-use	Pay-per-use
Region	Regions are geographic areas that are physically isolated from each other. The networks inside different regions are not connected to each other, so resources cannot be shared across different regions. For lower network latency and faster access to your resources, select the region nearest you. The region selected for the EIP is its geographical location. NOTE The geographical location of an EIP purchased in CN North-Ulanqab1 is Beijing.	CN-Hong Kong

Parameter	Description	Example Value
EIP Type	<ul style="list-style-type: none">• Dynamic BGP: Dynamic BGP provides automatic failover and chooses the optimal path when a network connection fails.• Static BGP: Static BGP offers more routing control and protects against route flapping, but an optimal path cannot be selected in real time when a network connection fails.• Premium BGP: Premium BGP chooses the optimal path and ensures low-latency and high-quality networks. BGP is used to interconnect with lines of multiple mainstream carriers. Public network connections that feature low latency and high quality are directly established between Chinese mainland and Hong Kong (China). (This parameter is available only in CN-Hong Kong.)• EIP Pool: This parameter is available only when you set Billing Mode to Pay-per-use. An EIP pool helps you manage a large number of EIPs and assigns EIPs with dynamic BGP routing, ensuring network stability and optimal user experience. <p>For details, see What Are the Differences Between Static BGP and Dynamic BGP?</p>	Dynamic BGP
EIP Pool	Select your purchased EIP pool. This parameter is available only when Billing Mode is set to Pay-per-use and EIP Type set to EIP Pool .	eipPool-test

Parameter	Description	Example Value
Billed By	<p>This parameter is available only when you set Billing Mode to Pay-per-use.</p> <ul style="list-style-type: none">• Bandwidth: You specify a maximum bandwidth and pay for the amount of time you use the bandwidth. This is suitable for scenarios with heavy or stable traffic.• Traffic: You specify a maximum bandwidth and pay for the total traffic you use. This is suitable for scenarios with light or sharply fluctuating traffic.• Shared Bandwidth: The bandwidth can be shared by multiple EIPs. This is suitable for scenarios with staggered traffic.	Bandwidth
Bandwidth	The bandwidth size in Mbit/s.	100
DDoS Protection	Cloud Native Anti-DDoS Basic Cloud Native Anti-DDoS Basic provides up to 5 Gbit/s of DDoS mitigation capacity. If the attack to an EIP exceeds 5 Gbit/s, the EIP will be blocked.	N/A
EIP Name	<p>The EIP name.</p> <p>The name can contain a maximum of 64 characters, which may consist of letters, digits, underscores (_), hyphens (-), and periods (.). The name cannot contain spaces.</p>	eip-test
Enterprise Project	<p>The enterprise project that the EIP belongs to.</p> <p>An enterprise project facilitates project-level management and grouping of cloud resources and users. The name of the default project is default.</p> <p>For details about creating and managing enterprise projects, see the Enterprise Management User Guide.</p>	default

Parameter	Description	Example Value
Advanced Settings	Click the drop-down arrow to configure parameters, including the bandwidth name and tag.	N/A
Bandwidth Name	The name of the bandwidth.	bandwidth
Tag	<p>The EIP tags. Each tag contains a key and value pair.</p> <p>The tag key and value must meet the requirements listed in Table 2-2.</p> <p>NOTE</p> <p>If your organization has created a tag policy for EIP, you need to add tags for EIP based on the tag policy. If a tag does not comply with the tagging rules, the creation may fail. Contact the organization administrator to learn details about the tag policy.</p>	<ul style="list-style-type: none">• Key: Ipv4_key1• Value: 3005eip
Monitoring	<p>Used to monitor the EIP and enabled by default.</p> <p>You can use the management console or APIs provided by Cloud Eye to query the metrics and alarms generated for the EIP and bandwidth.</p>	N/A
Required Duration	The duration for which the purchased EIP will use. The duration must be specified if the Billing Mode is set to Yearly/Monthly .	1 month
Auto-renew	<p>Whether to select Auto-renew. You can select it if the Billing Mode is set to Yearly/Monthly. The auto-renewal period is determined by the required duration.</p> <ul style="list-style-type: none">• Monthly subscription: The subscription is renewed every month.• Yearly subscription: The subscription is renewed each year.	N/A

Parameter	Description	Example Value
Quantity	The number of EIPs you want to purchase. The quantity must be specified if the Billing Mode is set to Pay-per-use .	1

Table 2-2 EIP tag requirements

Parameter	Requirement	Example Value
Key	<ul style="list-style-type: none">• Cannot be left blank.• Must be unique for each EIP.• Can contain a maximum of 36 characters.• Can contain letters, digits, underscores (_), and hyphens (-).	Ipv4_key1
Value	<ul style="list-style-type: none">• Can contain a maximum of 43 characters.• Can contain letters, digits, underscores (_), periods (.), and hyphens (-).	eip-01

 **NOTE**

- If you are buying an EIP billed on a pay-per-use basis and you want to use a shared bandwidth, you can only select an existing shared bandwidth from the **Bandwidth Name** drop-down list. If there are no shared bandwidths to select, purchase a shared bandwidth first.
 - A dedicated bandwidth cannot be changed to a shared bandwidth and vice versa. However, you can purchase a shared bandwidth for pay-per-use EIPs.
 - After an EIP is added to a shared bandwidth, the EIP will use the shared bandwidth.
 - After an EIP is removed from the shared bandwidth, the EIP will use the dedicated bandwidth.
3. Click **Next**.
 4. Click **Submit**.

If you click **Buy Shared Bandwidth** when you buy an EIP, you also need to purchase the bandwidth.

2.3 Binding an EIP to an Instance

Scenarios

After EIPs are assigned, you can bind them to resources such as ECSs, BMSs, virtual IP addresses, NAT gateways, and load balancers to allow them to access the Internet.

NOTE

An EIP and its bound cloud resource can use different billing modes.

Notes and Constraints

- An EIP can only be bound to an instance from its same region.
- An EIP can only be bound to an instance from its same account.
- An EIP cannot be bound to a frozen instance.

Procedure

Binding an EIP to an instance, such as an ECS, a BMS, or a virtual IP address

1. In the EIP list, locate the row that contains the EIP, and click **Bind**.
2. Select the instance.
3. Click **OK**.

NOTE

To bind an instance to an EIP:

- If the instance is an ECS:
 - The ECS must be in the running or stopped status.
 - The ECS must be in the same region as that of the EIP.
 - The ECS has no EIP bound.
- If the instance is a virtual IP address:
 - The virtual IP address must be in the same region as that of the EIP.
 - The virtual IP address must be in the available or assigned status.
- If the instance is a BMS:

The BMS must be in the same region as that of the EIP.

Binding an EIP to a NAT gateway

If you want to bind a NAT gateway to an EIP, the NAT gateway must be in the same region as that of the EIP. After an EIP is bound to a NAT gateway, ECSs associated with this gateway can share the EIP to access the Internet or provide services accessible from the Internet.

You can bind an EIP to a NAT gateway by configuring SNAT and DNAT rules for the gateway. For details, see [Configuring SNAT Rules to Enable Servers to Access the Internet](#) and [Configure DNAT Rules to Enable Servers to Provide Services Accessible from the Internet](#).

Binding an EIP to a load balancer

If you want to bind a load balancer to an EIP, the load balancer must be in the same region as that of the EIP. Then, the load balancer can receive requests over the Internet. For details, see [Binding or Unbinding an EIP](#).

No Instance Available for EIP Binding

- There are no instances available when you want to bind an instance to an EIP.

You have instances, but an EIP cannot be bound to any of them.

- An EIP cannot be bound to an instance from a different region.
- An EIP cannot be bound to an instance from a different account.
- The instance is frozen and cannot have an EIP bound.

There are no instances.

[Buy an ECS](#), [create a BMS](#), or [assign a virtual IP address](#).

2.4 Unbinding an EIP from an Instance

Scenarios

Unbind an EIP from an instance, if:

- Your instance does not need to use an EIP.
If you do not release the EIP after unbinding it, the EIP will be billed. For details, see [Releasing or Unsubscribing an EIP](#).
- You want to bind the EIP to another instance.

Notes and Constraints

- An EIP cannot be unbound if its server is suspected of violations and the EIP is frozen by the national supervision department.
For details, see [Why My EIPs Are Frozen? How Do I Unfreeze My EIPs?](#)
- Your account will be frozen if it is in arrears and you cannot perform any operations on pay-per-use resources in the retention period. After you top up your account, you will be billed for expenditures generated by the pay-per-use EIPs. You can view the expenditures on the [Overview](#) page of the Billing Center.

Unbinding an EIP from an ECS, BMS, or Virtual IP Address

Unbinding a single EIP

1. Go to the [EIP list](#) page.
2. On the displayed page, locate the row that contains the target EIP, and click **Unbind** in the **Operation** column.

A confirmation dialog box is displayed.

3. Click **Yes** in the displayed dialog box.

In the EIP list, the target EIP has no associated instance.

Unbinding multiple EIPs at a time

1. Go to the [EIP list](#) page.
2. On the displayed page, select the EIPs to be unbound.
3. In the upper left corner of the EIP list, click **Unbind**.
A confirmation dialog box is displayed.
4. Click **Yes** in the displayed dialog box.
In the EIP list, the target EIPs have no associated instances.

Unbinding an EIP from Other Instances

Unbinding an EIP from a NAT gateway

You can unbind an EIP from a NAT gateway by deleting the SNAT and DNAT rules. For details, see [Deleting a DNAT Rule](#) and [Deleting an SNAT Rule](#).

Unbinding an EIP from a load balancer

You can unbind an EIP from a load balancer on the ELB console. For details, see [Binding or Unbinding an EIP](#).

NOTE

If a pay-per-use EIP is unbound from an instance, the EIP will be billed to keep it allocated to your account unless it is released.

If an EIP billed by bandwidth is unbound from an instance, the bandwidth will continue to be billed.

If you have any questions about the billing, see [Why Am I Still Being Billed After My EIP Has Been Unbound or Released?](#)

2.5 Releasing or Unsubscribing an EIP

Scenarios

If an EIP is no longer required, you can unbind it from your instance and release it if it is a pay-per-use EIP or unsubscribe from it if it is a yearly/monthly EIP. If you do not release or unsubscribe from the EIP in a timely manner after unbinding it, the EIP continues to be billed. This section describes how to release or unsubscribe from an EIP.

Notes and Constraints

- An EIP that has been bound to an instance cannot be released or unsubscribed from.
- Yearly/Monthly EIPs can only be unsubscribed from.
- An EIP cannot be released or unsubscribed from if its server is suspected of violations and the EIP is frozen by the national supervision department.
- The system preferentially assigns EIPs to you from the ones you released or unsubscribed from, if any. However, if any of these EIPs is already assigned to another user, it cannot be re-assigned to you.

For details, see [How Do I Assign or Retrieve a Specific EIP?](#)

Releasing a Pay-per-Use EIP

1. Go to the [EIP list](#) page.
2. In the EIP list, locate the row that contains the EIP and choose **More > Release** in the **Operation** column.
A confirmation dialog box is displayed.
3. Click **Yes** in the displayed dialog box.
You can find that the EIP is not in the EIP list.

You can also select multiple EIPs and choose **More > Release** above the list to release pay-per-use EIPs.

Unsubscribing From a Yearly/Monthly EIP

1. Go to the [EIP list](#) page.
2. In the EIP list, locate the target EIP, and choose **More > Unsubscribe** in the **Operation** column. The unsubscription page is displayed.
3. Confirm the information and click **Confirm**. A confirmation dialog box is displayed.
4. Confirm the information and click **Yes**.
You can find that the EIP is not in the EIP list.

You can also select multiple EIPs and choose **More > Unsubscribe** above the list to unsubscribe yearly/monthly EIPs.

Scenarios Where EIPs Cannot Be Released or Unsubscribed from

- The EIP has been bound to an instance.
Only EIPs that have no instances bound can be released or unsubscribed from. To release or unsubscribe from an EIP that has been bound to an instance, unbind it first. For details, see [Unbinding an EIP from an Instance](#).
- Yearly/Monthly EIPs
Yearly/Monthly EIPs cannot be released. If you no longer need them, you can [unsubscribe](#) them.
- Frozen EIPs
An EIP cannot be released or unsubscribed if its server is suspected of violations and the EIP is frozen by the national supervision department. For details, see [Why My EIPs Are Frozen? How Do I Unfreeze My EIPs?](#)

2.6 Changing Dedicated Bandwidth Size of an EIP

Scenarios

No matter which billing mode is used, if your EIP is not added to a shared bandwidth, it uses a dedicated bandwidth. A dedicated bandwidth can control how much data can be transferred using a single EIP.

This section describes how to increase or decrease the bandwidth size. Changing bandwidth size does not change the EIPs.

When you change the bandwidth size, the bandwidth price and effective time depend on the billing mode, which applies to both dedicated and shared bandwidths. For details, see [Table 2-3](#).

 **NOTE**

Decreasing bandwidths may cause packet loss.

If the maximum bandwidth cannot meet your service requirements, you can [submit a service ticket](#) to request a higher quota.

Table 2-3 Impact on billing after bandwidth size change

Billing Mode	Billed By	Change	Impact
Yearly/ Monthly	Bandwidth	Increase bandwidth	The change will take effect immediately. The increased bandwidth will be billed accordingly.
Yearly/ Monthly	Bandwidth	Decrease bandwidth upon renewal	The change will not take effect immediately. You need to select a new bandwidth size and a renewal duration. The change will take effect in the first billing cycle after a successful renewal. <ul style="list-style-type: none">• The order can be unsubscribed before the bandwidth takes effect.• The bandwidth cannot be modified in the current billing cycle.
Yearly/ Monthly	Bandwidth	Decrease bandwidth immediately	The change will take effect immediately.
Pay-per-use	Bandwidth	Increase or decrease the bandwidth	The change will take effect immediately.
Pay-per-use	Traffic	Increase or decrease the bandwidth	The change will take effect immediately. The bandwidth size you set is only used to limit the maximum data transfer rate.

Notes and Constraints

- If you renew a yearly/monthly EIP in its current validity period, its bandwidth cannot be modified in this period.
- If an EIP is frozen due to account arrears or for security reasons, its dedicated bandwidth cannot be modified.

Procedure

1. Go to the [EIP list](#) page.

2. Locate the row that contains the target EIP in the EIP list, and click **More > Modify Bandwidth** in the **Operation** column.
 - If it is a pay-per-use EIP, the **Modify Bandwidth** page is displayed.
 - If it is a yearly/monthly EIP, select either of the following method to increase or decrease the bandwidth and click **Continue**.
 - Increase bandwidth
 - Decrease bandwidth immediately
 - Decrease bandwidth
3. Change the bandwidth size as prompted.

Figure 2-3 Modifying the bandwidth of a pay-per-use EIP

< | Modify Bandwidth

Current Configuration

Bandwidth Name	bandwidth	EIP	119
Bandwidth (Mbit/s)	1	Billed By	Bandwidth
Bandwidth Type	Dedicated		

New Configuration

* Bandwidth Name

* Billed By Bandwidth Traffic

* Bandwidth (Mbit/s) The value ranges from 1 to 500 Mbit/s.

New Price: \$0 USD/hour

Figure 2-4 Modifying the bandwidth of a yearly/monthly EIP

< | Modify Bandwidth

Current Configuration

Bandwidth Name	bandwidth	EIP	119
Bandwidth (Mbit/s)	1	Billed By	Bandwidth
Bandwidth Type	Dedicated		

New Configuration

* Bandwidth Name

* Billed By Bandwidth Traffic

* Bandwidth (Mbit/s) The value ranges from 1 to 500 Mbit/s.

Price: \$0

NOTE

You can also change the bandwidth name. If an EIP is billed on a pay-per-use basis, you can change its bandwidth billing option.

4. Click **Next**.

5. Click **Submit**.

If you select **Decrease bandwidth immediately**, click **Submit**.

You can also select multiple EIPs and click **Modify Bandwidth** above the EIP list to modify bandwidths in batches. Only multiple dedicated bandwidths of pay-per-use EIPs can be modified at a time.

2.7 Modifying an EIP Bandwidth

Scenarios

No matter which billing mode is used, if your EIP is not added to a shared bandwidth, it uses a dedicated bandwidth. A dedicated bandwidth can control how much data can be transferred using a single EIP.

This section describes how to increase or decrease the bandwidth size. Changing bandwidth size does not change the EIPs.

When you change the bandwidth size, the bandwidth price and effective time depend on the billing mode, which applies to both dedicated and shared bandwidths. For details, see [Table 2-4](#).

 **NOTE**

Decreasing bandwidths may cause packet loss.

If the maximum bandwidth cannot meet your service requirements, you can [submit a service ticket](#) to request a higher quota.

Table 2-4 Impact on billing after bandwidth size change

Billing Mode	Billed By	Change	Impact
Yearly/ Monthly	Bandwidth	Increase bandwidth	The change will take effect immediately. The increased bandwidth will be billed accordingly.
Yearly/ Monthly	Bandwidth	Decrease bandwidth upon renewal	The change will not take effect immediately. You need to select a new bandwidth size and a renewal duration. The change will take effect in the first billing cycle after a successful renewal. <ul style="list-style-type: none">• The order can be unsubscribed before the bandwidth takes effect.• The bandwidth cannot be modified in the current billing cycle.
Yearly/ Monthly	Bandwidth	Decrease bandwidth immediately	The change will take effect immediately.

Billing Mode	Billed By	Change	Impact
Pay-per-use	Bandwidth	Increase or decrease the bandwidth	The change will take effect immediately.
Pay-per-use	Traffic	Increase or decrease the bandwidth	The change will take effect immediately. The bandwidth size you set is only used to limit the maximum data transfer rate.

Procedure

- Go to the [EIP list](#) page.
- Locate the EIP whose bandwidth you want to modify, choose **More > Modify Bandwidth** in the **Operation** column.
 - If it is a pay-per-use EIP, the **Modify Bandwidth** page is displayed.
 - If it is a yearly/monthly EIP, select either of the following method to increase or decrease the bandwidth and click **Continue**.
 - Increase bandwidth
 - Decrease bandwidth immediately
 - Decrease bandwidth
- Modify the bandwidth parameters as prompted.

Figure 2-5 Modifying the bandwidth of a pay-per-use EIP




Figure 2-6 Modifying the bandwidth of a yearly/monthly EIP

The screenshot shows a 'Modify Bandwidth' interface. At the top, there is a breadcrumb '< | Modify Bandwidth'. Below this, the 'Current Configuration' is displayed in a table:

Current Configuration			
Bandwidth Name	bandwidth	EIP	119
Bandwidth (Mbit/s)	1	Billed By	Bandwidth
Bandwidth Type	Dedicated		

Below the current configuration, the 'New Configuration' section contains three fields:

- * Bandwidth Name:** A text input field containing 'bandwidth'.
- * Billed By:** A dropdown menu currently set to 'Bandwidth'.
- * Bandwidth (Mbit/s):** A numeric input field with a value of '1' and a range indicator: 'The value ranges from 1 to 500 Mbit/s'.

At the bottom left, there is a 'Price:' label followed by a greyed-out field. At the bottom right, there is a black button labeled 'Next'.

4. Click **Next**.
5. Click **Submit**.

You can also select multiple EIPs and click **Modify Bandwidth** above the list to modify their bandwidths in batches. Only dedicated bandwidths billed on a pay-per-use basis can be modified in batches.

Helpful Links

- [How Do I Change the EIP Billing Option from Bandwidth to Traffic or from Traffic to Bandwidth?](#)
- [Can I Increase My Bandwidth Billed on Yearly/Monthly Basis and Then Decrease It?](#)

2.8 Exporting EIP Information

Scenarios

The information of all EIPs under your account can be exported in an Excel file to a local directory. The file records the ID, status, type, bandwidth name, and bandwidth size of EIPs.

Procedure

1. Go to the [EIP list](#) page.
2. On the EIP list page, select one or more EIPs and click **Export** in the upper left corner.

The system will automatically export all EIPs to an Excel file and download the file to a local directory.

2.9 Managing EIP Tags

Scenarios

Tags can be added to EIPs to facilitate EIP identification and administration. You can add a tag to an EIP when assigning the EIP. Alternatively, you can add a tag to an assigned EIP on the EIP details page. A maximum of 20 tags can be added to each EIP.

If your organization has created a tag policy for EIP, you need to add tags for EIP based on the tag policy. If a tag does not comply with the tagging rules, the EIP may fail to be created or the tag may fail to be added. Contact the organization administrator to learn more about the tag policy.

NOTE

The Organizations service is in open beta test (OBT). To use organization rules, apply for OBT.

A tag consists of a key and value pair. [Table 2-5](#) lists the tag key and value requirements.

Table 2-5 EIP tag requirements

Parameter	Requirement	Example Value
Key	<ul style="list-style-type: none">• Cannot be left blank.• Must be unique for each EIP.• Can contain a maximum of 36 characters.• Can contain letters, digits, underscores (_), and hyphens (-).	Ipv4_key1
Value	<ul style="list-style-type: none">• Can contain a maximum of 43 characters.• Can contain letters, digits, underscores (_), periods (.), and hyphens (-).	eip-01

Procedure

Searching for EIPs by tag key and value on the EIP list page

1. Go to the [EIP list](#) page.
2. In the search box above the EIP list, click anywhere in the box to set filters.
Select the tag key and then the value as required. The system filters resources based on the tag you select.

Adding, deleting, editing, and viewing tags on the Tags tab of an EIP

1. Go to the [EIP list](#) page.

2. On the displayed page, locate the EIP whose tags you want to manage and click the EIP name.
3. On the page showing EIP details, click the **Tags** tab and perform desired operations on tags.

- View tags.

On the **Tags** tab, you can view details about tags added to the current EIP, including the number of tags and the key and value of each tag.

- Add a tag.

Click **Edit Tag** in the upper left corner. In the displayed dialog box, click **Add Tag**, enter the tag key and value, and click **OK**.

- Edit a tag.

Click **Edit Tag** in the upper left corner. In the displayed dialog box, enter the tag key and value, and click **OK**.

The tag key cannot be modified.

- Delete a tag.

Click **Edit Tag** in the upper left corner. In the displayed dialog box, click **Delete** in the row that contains the target tag, and click **OK**.

2.10 IPv6 EIP

2.10.1 IPv6 EIP Overview

Overview

Both IPv4 and IPv6 EIPs are available. You can assign an IPv6 EIP or map an existing IPv4 EIP to an IPv6 EIP.

After the IPv6 EIP function is enabled, you will obtain both an IPv4 EIP and its corresponding IPv6 EIP. External IPv6 addresses can access cloud resources through this IPv6 EIP.


IPv4 EIPs are billed. IPv6 EIPs are currently free, but will be billed at a later date (price yet to be determined).

Application Scenarios of IPv4/IPv6 Dual Stack

If your ECS supports IPv6, you can use the IPv4/IPv6 dual stack. For details about application scenarios and resource planning, see [Table 2-6](#).

The ECS flavors that support IPv6 vary depending on regions and AZs. Check whether an ECS flavor supports IPv6 after you select a region and AZ on the management console.

Figure 2-7 Checking whether an ECS flavor supports IPv6



If the value of **IPv6** is **Yes** for an ECS flavor, the flavor supports IPv6.

NOTE

AZ and **Flavor** determine whether IPv6 is supported.

After you select an AZ, if **IPv6** is not displayed or the value of **IPv6** is **No**, IPv6 is not supported by any or certain flavors in the AZ.

Table 2-6 Application scenarios of IPv4/IPv6 dual stack

Application Scenario	Description	Requirement	IPv4 or IPv6 Subnet	ECS
Private IPv4 communication	Your applications on ECSs need to communicate with other systems (such as databases) through private networks using IPv4 addresses.	<ul style="list-style-type: none"> No EIPs have been bound to the ECSs. 	IPv4 CIDR Block	Private IPv4 address: used for private IPv4 communication.

Application Scenario	Description	Requirement	IPv4 or IPv6 Subnet	ECS
Public IPv4 communication	Your applications on ECSs need to communicate with other systems (such as databases) through public IPv4 addresses.	<ul style="list-style-type: none">EIPs have been bound to the ECSs.	IPv4 CIDR Block	<ul style="list-style-type: none">Private IPv4 address: used for private IPv4 communication.Public IPv4 address: used for public IPv4 communication.

Application Scenario	Description	Requirement	IPv4 or IPv6 Subnet	ECS
Private IPv6 communication	Your applications on ECSs need to communicate with other systems (such as databases) through private IPv6 addresses.	<ul style="list-style-type: none">• IPv6 has been enabled for the VPC subnet.• The network has been configured for the ECSs as follows:<ul style="list-style-type: none">– Flavor: Any ECS flavor that supports the IPv6 network. For details, see section "x86 ECS Specifications and Types" in the Elastic Cloud Server User Guide.– VPC and Subnet: IPv6-enabled subnet and VPC.– Self-assigned IPv6 address: Selected.– Shared Bandwidth: Selected Do not configure.	<ul style="list-style-type: none">• IPv4 CIDR Block• IPv6 CIDR block	<ul style="list-style-type: none">• Private IPv4 address + IPv4 EIP: Bind an IPv4 EIP to the instance to allow public IPv4 communication.• Private IPv4 address: Do not bind any IPv4 EIP to the instance and use only the private IPv4 address to allow private IPv4 communication.• IPv6 address: Do not configure shared bandwidth for the IPv6 address to allow private IPv6 communication.

Application Scenario	Description	Requirement	IPv4 or IPv6 Subnet	ECS
Public IPv6 communication	An IPv6 network is required for the ECS to access the IPv6 service on the Internet.	<ul style="list-style-type: none"> IPv6 has been enabled for the VPC subnet. The network has been configured for the ECSs as follows: <ul style="list-style-type: none"> Flavor: Any ECS flavor that supports the IPv6 network. For details about the ECS flavor that support the IPv6 network, see section "x86 ECS Specifications and Types" in the Elastic Cloud Server User Guide. VPC and Subnet: IPv6-enabled subnet and VPC. Self-assigned IPv6 address: Selected. Shared Bandwidth: Selected a shared bandwidth. <p>NOTE For details, see Setting Up an IPv6 Network.</p>	<ul style="list-style-type: none"> IPv4 CIDR Block IPv6 CIDR block 	<ul style="list-style-type: none"> Private IPv4 address + IPv4 EIP: Bind an IPv4 EIP to the instance to allow public IPv4 communication. Private IPv4 address: Do not bind any IPv4 EIP to the instance and use only the private IPv4 address to allow private IPv4 communication. IPv6 address + shared bandwidth: Allow both private IPv6 communication and public IPv6 communication.

For details, see [IPv4 and IPv6 Dual-Stack Network](#).

Application Scenarios of IPv6 EIP

If you want an ECS to provide IPv6 services but the ECS does not support IPv6 networks or you do not want to build an IPv6 network, you can use IPv6 EIP to


quickly address your requirements. For details about application scenarios and resource planning, see [Table 2-7](#).

Table 2-7 Application scenarios and resource planning of an IPv6 EIP network (with IPv6 EIP enabled)

Application Scenario	Description	Requirement	IPv4 or IPv6 Subnet	ECS
Public IPv6 communication	You want to allow an ECS to provide IPv6 services for clients on the Internet without setting up an IPv6 network.	<ul style="list-style-type: none">• An EIP has been bound to the ECS.• IPv6 EIP has been enabled.	IPv4 CIDR Block	<ul style="list-style-type: none">• Private IPv4 address: used for private IPv4 communication.• IPv4 EIP (with IPv6 EIP enabled): used for public network communication through IPv4 and IPv6 addresses.

Application Scenarios and Resource Planning of IPv6 Networks

Figure 2-8 Application scenarios and resource planning of IPv6 networks



2.10.2 Assigning or Releasing an IPv6 EIP

Scenarios

If you want an ECS to provide IPv6 services but the ECS does not support IPv6 networks or you do not want to build an IPv6 network, you can use an IPv6 EIP to quickly address your requirements.

Enabling IPv6 EIP

- Method 1:

Apply for an EIP with **IPv6 EIP** enabled by referring to section [Assigning an EIP](#).

After the IPv6 EIP is enabled, you will obtain both an IPv4 EIP and an IPv6 EIP. External IPv6 addresses can access cloud resources through this IPv6 EIP.

- Method 2:

If you want an IPv6 EIP in addition to an existing IPv4 EIP, locate the row that contains the target IPv4 EIP, click **More** in the **Operation** column, and select **Enable IPv6 EIP**. Then, a corresponding IPv6 EIP will be assigned.

After the IPv6 EIP is enabled, you will obtain both an IPv4 EIP and an IPv6 EIP. External IPv6 addresses can access cloud resources through this IPv6 EIP.

 **NOTE**

There is no adverse impact on the cloud resources bound with existing IPv4 EIPs.

Configuring Security Groups

After the IPv6 EIP is enabled, you need to configure security group rules to allow traffic to and from 198.19.0.0/16. For details about the security group rules, see [Table 2-8](#). IPv6 EIP uses NAT64 to convert the source IP address in the inbound direction to an IPv4 address in the IP address range 198.19.0.0/16. The source port can be a random one, the destination IP address is the private IPv4 address of your local server, and the destination port remains unchanged.

For details, see [Virtual Private Cloud User Guide](#).

Table 2-8 Security group rules

Direction	Protocol	Source or Destination
Inbound	All NOTE Configure security group rules as required.	Source: 198.19.0.0/16
Outbound	All	Destination: 198.19.0.0/16

Disabling IPv6 EIP

If you do not need the IPv6 EIP, locate the row that contains its corresponding IPv4 EIP, click **More** in the **Operation** column, and select **Disable IPv6 EIP**. Then, the IPv6 EIP will be released. You will only have the IPv4 EIP.

3 EIP Billing

3.1 Changing EIP Billing Mode

Scenarios

The EIP service provides multiple billing modes for you to select. You can change your EIP billing mode during the EIP usage period if necessary.

 **NOTE**

Changing the billing mode does not change EIPs or interrupt their use.

Table 3-1 describes the details of changing EIP billing modes.

Table 3-1 EIP billing mode change description

Change	Description
From yearly/monthly to pay-per-use	<ul style="list-style-type: none">An EIP billed on a yearly/monthly basis can be directly changed to be billed by bandwidth on a pay-per-use basis immediately or upon expiration.An EIP billed on a yearly/monthly basis cannot be directly changed to be billed by traffic on a pay-per-use basis. To change this:<ol style="list-style-type: none">Change the EIP to be billed by bandwidth on a pay-per-use basis.Change the EIP to be billed by traffic on a pay-per-use basis. <p>The new billing mode takes effect only after the yearly/monthly subscription expires, if you want to change the EIP to be billed by bandwidth on a pay-per-use basis upon expiration. The new billing mode takes effect immediately, if you want to change the EIP to be billed by bandwidth on a pay-per-use basis immediately.</p>
From pay-per-use to yearly/monthly	<ul style="list-style-type: none">An EIP that is billed by bandwidth on a pay-per-use basis can be directly changed to be billed on a yearly/monthly basis.An EIP that is billed by traffic on a pay-per-use basis cannot be directly changed to be billed on a yearly/monthly basis. To change this:<ol style="list-style-type: none">Change the EIP to be billed by bandwidth on a pay-per-use basis.Change the EIP to be billed on a yearly/monthly basis. <p>The new billing mode takes effect immediately.</p>
<ul style="list-style-type: none">From billing by traffic (pay-per-use) to billing by bandwidth (pay-per-use)From billing by bandwidth (pay-per-use) to billing by traffic (pay-per-use)	<ul style="list-style-type: none">An EIP billed by traffic on a pay-per-use basis can be directly changed to be billed by bandwidth on a pay-per-use basis.An EIP billed by bandwidth on a pay-per-use basis can be directly changed to be billed by traffic on a pay-per-use basis. <p>The new billing mode takes effect immediately.</p>

The operation guides are as follows:

- [From Yearly/Monthly to Pay-Per-Use upon Expiration \(Billed by Bandwidth\)](#)

- [From Yearly/Monthly to Pay-Per-Use Immediately \(Billed by Bandwidth\)](#)
- [From Pay-per-Use \(Billed by Bandwidth\) to Yearly/Monthly](#)
- [Pay-per-Use EIPs: From Billing By Traffic to By Bandwidth](#)

From Yearly/Monthly to Pay-Per-Use upon Expiration (Billed by Bandwidth)

1. Go to the [EIP list](#) page.
2. In the EIP list, change billing mode of a single EIP or multiple EIPs from yearly/monthly to pay-per-use (billed by bandwidth):
 - Single EIP:
Locate the row that contains the EIP and choose **More > Change to Pay-per-Use upon Expiration** in the **Operation** column.
 - Multiple EIPs:
Select the EIPs in the EIP list and choose **More > Change to Pay-per-Use upon Expiration** in the upper left corner of the list.
3. In the displayed dialog box, confirm the information and click **Yes**.
You are switched to a page of the Billing Center.
4. Confirm the information and click **Change to Pay-per-Use**.

From Yearly/Monthly to Pay-Per-Use Immediately (Billed by Bandwidth)

1. Go to the [EIP list](#) page.
2. In the EIP list, change billing mode of a single EIP or multiple EIPs from yearly/monthly to pay-per-use (billed by bandwidth):
 - Single EIP:
Locate the row that contains the EIP and choose **More > Change to Pay-per-Use Immediately** in the **Operation** column.
 - Multiple EIPs:
Select the EIPs in the EIP list and choose **More > Change to Pay-per-Use Immediately** in the upper left corner of the list.
3. In the displayed dialog box, confirm the information and click **Yes**.
You are switched to a page of the Billing Center.
4. Confirm the information and click **Change to Pay-per-Use**.

From Pay-per-Use (Billed by Bandwidth) to Yearly/Monthly

1. Go to the [EIP list](#) page.
2. In the EIP list, change the billing mode of a single EIP or multiple EIPs from pay-per-use (billed by bandwidth) to yearly/monthly.
 - Single EIP:
Locate the row that contains the EIP and choose **More > Change Billing Mode** in the **Operation** column.
 - Multiple EIPs:
Select EIPs and choose **More > Change Billing Mode** in the upper left corner of the EIP list.

3. In the displayed dialog box, confirm the information and click **Yes**.
4. On the **Change Subscriptions** page, set parameters such as **Renewal Duration**.
5. Click **Pay**.

Pay-per-Use EIPs: From Billing By Traffic to By Bandwidth

1. Go to the [EIP list](#) page.
2. In the EIP list, locate the row that contains the EIP, click **More** in the **Operation** column, and click **Modify Bandwidth**.
3. On the **Modify Bandwidth** page, change the billing option as prompted.
You can also change the bandwidth name and size.
4. Click **Next**.
5. On the displayed page, confirm the configurations and click **Submit**.

3.2 Renewing a Yearly/Monthly EIP

Scenarios

You can renew a yearly/monthly EIP to extend its expiration date.

If your yearly/monthly resource is expired and is not renewed, the resource enters the grace period. If you do not renew the monthly/yearly resource within the grace period, the resource enters a retention period after the grace period has expired. You cannot perform any operations on yearly/monthly resources that are in the grace or retention period. For example, you cannot change your bandwidth if it is in the grace period or retention period.

This section describes how to renew an EIP. Renewing EIPs does not change EIPs.

Procedure

1. Go to the [EIP list](#) page.
2. In the EIP list, renew a single EIP or multiple EIPs.
 - Renewing a single EIP:
Locate the row that contains the EIP, and choose **More > Renew** in the **Operation** column.
 - Renewing multiple EIPs at once:
 - i. Select the EIPs in the EIP list and click **Renew** in the upper left corner of the list.
 - ii. In the displayed dialog box, confirm the information and click **Yes**.
3. On the **Renew** page, set the following parameters:
 - **Renewal Duration**: Select a renewal period as required.
 - **Renewal Date**: The new renewal date may result in slightly different subscription lengths for different resources.
4. Click **Pay**.

3.3 Viewing the EIP Billing Information


Scenarios

This section describes how to view the billing details of EIPs and their bandwidths.
To view the bandwidth usage, see [Viewing Metrics](#).

Procedure

1. Log in to the management console.
2. In the upper right corner of the page, choose **Billing** > **Bills**.

Figure 3-1 Bills



3. In the navigation pane on the left, choose **Billing** > **Transactions and Detailed Bills**.
4. Click **Transaction Bills** and select the billing cycle to be viewed.
5. In the transaction bill list, locate the row that contains the target transaction bill and click **Details** in the **Operation** column.
6. View details of the transaction bill.

4 EIP Pool

4.1 EIP Pool Overview

An EIP pool helps you manage a large number of EIPs and assigns EIPs with dynamic BGP routing, ensuring network stability and optimal user experience. The price of an EIP pool is subject to that displayed on the EIP pool console.

Notes and Constraints

- If your EIP is allocated from an EIP pool, you only need to pay for the bandwidth associated with the EIP.
- The billing mode of an EIP from an EIP pool cannot be changed to yearly/monthly.

4.2 Purchasing an EIP Pool

Scenarios

EIP pools can only be billed on a yearly/monthly basis. The price of an EIP pool is subject to that displayed on the EIP pool console. You can purchase multiple EIP pools.

EIPs allocated from EIP pools do not occupy your EIP quota.

Procedure

1. In the upper right corner, click [Buy EIP Pool](#).
2. Set the parameters as prompted.

Table 4-1 Parameter description

Item	Parameter	Description	Example Value
Basic Configuration	Billing Mode	The billing mode of the EIP pool. EIP pools are billed on a yearly/monthly basis.	Yearly/Monthly
Basic Configuration	Region	Regions are geographic areas that are physically isolated from each other. The networks inside different regions are not connected to each other, so resources cannot be shared across different regions. For lower network latency and faster access to your resources, select the region nearest to your target users.	-
EIP Pool	EIP Type	Dynamic BGP Pool	Dynamic BGP Pool
EIP Pool	EIP Quota	The number of EIPs in the EIP pool. An EIP pool assigns EIPs with dynamic BGP routing, ensuring network stability and optimal user experience. You can assign EIPs within the EIP quota configured for the EIP pool.	50
Basic Information	Name	The name of the EIP pool. The name is 1–36 characters long and can contain only letters, digits, underscores (_), hyphens (-), and periods (.).	eipPool-test
Basic Information	Description	Supplementary information about the EIP pool. This parameter is optional. The description can contain a maximum of 255 characters and cannot contain angle brackets (<>).	-

Item	Parameter	Description	Example Value
Basic Information	Required Duration	Required duration of the EIP pool. Plan the required duration as required because an EIP pool cannot be unsubscribed from.	3 months
Basic Information	Auto-renew	Whether to select Auto-renew . You can select it if the Billing Mode is set to Yearly/Monthly . The auto-renewal period is determined by the purchase duration. <ul style="list-style-type: none">• Monthly subscription: The subscription is renewed every month.• Yearly subscription: The subscription is renewed each year.	-

3. Click **Next**.

Related Operations

If you need to buy pay-per-use EIPs, you can select the EIP pool to assign EIPs. For details, see [Assigning an EIP](#).

If your EIP is allocated from an EIP pool, you only need to pay for the bandwidth associated with the EIP.

4.3 Modifying an EIP Pool

Scenarios

You can modify the quota of EIPs in an EIP pool.

Procedure

1. Go to the [EIP pool list page](#).
2. Locate the row that contains the EIP pool to be modified and click **Modify** in the **Operation** column. On the displayed **Modify EIP Pool** page, modify the EIP quota.

You can decrease or increase the quota as required. The change is applied immediately.

- Decreasing the EIP quota
 - i. Select or enter a lower quota and click **Next**.

- ii. Confirm the configuration and submit your request.
- Increasing the EIP quota
 - i. Select or enter a higher quota and click **Next**.
 - ii. Confirm the configuration and click **Pay Now**.
 - iii. On the payment page, select a payment method and click **Confirm**.

4.4 Unsubscribing from an EIP Pool

Scenarios

You can unsubscribe from an EIP pool that is no longer needed. You will only be billed for the time you used the EIP pool.

Procedure

1. Go to the [EIP pool list page](#).
2. Locate the EIP pool you want to unsubscribe from and click **Unsubscribe** in the **Operation** column.
3. On the **Unsubscribe from Resource** page, click **Confirm**.

4.5 Renewing an EIP Pool

Scenarios

If your EIP pool is about to expire, you can renew it to extend the validity period.

Procedure

1. Go to the [EIP pool list page](#).
2. Locate the EIP pool to be renewed and click **Renew** in the **Operation** column.
3. On the **Renew** page, set the renewal duration.
4. Set **Renewal Date**.
The new renewal date may extend the subscription based on the current subscription. You can check the renewal information in the table on the **Renew** page.
5. On the payment page, confirm the order information and click **Confirm**.

5 Shared Bandwidth

5.1 Shared Bandwidth Overview

A shared bandwidth can be shared by multiple EIPs and controls the data transfer rate on these EIPs in a centralized manner. All ECSs and load balancers that have EIPs bound in the same region can share a bandwidth.

NOTE

- A shared bandwidth cannot control how much data can be transferred using a single EIP. Data transfer rate on EIPs cannot be customized.

When you host a large number of applications on the cloud, if each EIP uses a bandwidth, a lot of bandwidths are required, which significantly increases bandwidth costs. If all EIPs share the same bandwidth, you can lower bandwidth costs and easily perform system O&M.

- Lowered Bandwidth Costs
Region-level bandwidth sharing and multiplexing reduce bandwidth usage and O&M costs.
- Flexible Operations
You can add pay-per-use EIPs (except for **5_gray** EIPs of dedicated load balancers) to or remove them from a shared bandwidth regardless of the type of instances that they are bound to.
- Flexible Billing Modes
The yearly/monthly and pay-per-use billing modes are provided.

You can use a shared bandwidth in either of the following ways:

- Assign a shared bandwidth and add your pay-per-use EIPs to the bandwidth.
 - [Assigning a Shared Bandwidth](#)
 - [Adding EIPs to a Shared Bandwidth](#)
- Assign a shared bandwidth, set **Billed By** to **Shared Bandwidth** and select the shared bandwidth when you assign EIPs.
 - [Assigning a Shared Bandwidth](#)

- [Assigning an EIP](#)

Shared Bandwidth Quotas

- Each account can have a maximum of 5 shared bandwidths. If you need more shared bandwidths, submit a service ticket to request a quota increase.
- If you want to increase a pay-per-use shared bandwidth that is greater than 1 Gbit/s, the minimum increase is 500 Mbit/s.

Notes and Constraints

- The minimum size of a shared bandwidth that can be purchased is 5 Mbit/s. You can only add pay-per-use EIPs to a shared bandwidth.
- If a yearly/monthly shared bandwidth is deleted upon expiration, EIPs sharing the bandwidth will be removed from the bandwidth and be billed based on the mode before they are added to the shared bandwidth.
- A shared bandwidth can only be used by resources from its same account.

NOTE

- A dedicated bandwidth cannot be changed to a shared bandwidth and vice versa. However, you can purchase a shared bandwidth for pay-per-use EIPs.
 - Add an EIP to a shared bandwidth and then the EIP will use the shared bandwidth.
 - Remove the EIP from the shared bandwidth and then the EIP will use the dedicated bandwidth.
- If you want to submit a service ticket, refer to [Submitting a Service Ticket](#).

5.2 Assigning a Shared Bandwidth

Scenarios

When you host a large number of applications on the cloud, if each EIP uses dedicated bandwidth, a lot of bandwidths are required, which incurs high costs. If all EIPs share the same bandwidth, your network operation costs will be lowered and your system O&M as well as resource statistics will be simplified.

Assign a shared bandwidth for use with EIPs.

Procedure

1. Go to the [Buy Shared Bandwidth](#) page.
2. Set the parameters as prompted.

Table 5-1 Parameter descriptions

Parameter	Description	Example Value
Billing Mode	A shared bandwidth can be billed on a yearly/monthly or pay-per-use basis. <ul style="list-style-type: none">● Yearly/Monthly: You pay for the bandwidth by year or month before using it. No other charges apply during the validity period of the bandwidth.● Pay-per-use: You pay for the bandwidth based on the amount of time you use the bandwidth.	Yearly/Monthly
Region	Regions are geographic areas that are physically isolated from each other. The networks inside different regions are not connected to each other, so resources cannot be shared across different regions. For lower network latency and faster access to your resources, select the region nearest you.	CN-Hong Kong
Bandwidth Type	Select a type of the shared bandwidth based on your EIP type. <ul style="list-style-type: none">● Standard: Dynamic BGP and premium BGP EIPs can be added to a shared bandwidth of this type.● Premium BGP: Premium BGP EIPs can be added to a shared bandwidth of this type. NOTE In the CN-Hong Kong region, only dynamic BGP EIPs can be added to standard shared bandwidths.	Standard
Billed By	The billing method for the shared bandwidth. You can specify a shared bandwidth to be billed by bandwidth.	Bandwidth
Bandwidth	The bandwidth size in Mbit/s. The minimum value is 5 Mbit/s.	10
Enterprise Project	The enterprise project that the EIP belongs to. An enterprise project facilitates project-level management and grouping of cloud resources and users. The name of the default project is default .	default
Name	The name of the shared bandwidth.	Bandwidth-001

Parameter	Description	Example Value
Required Duration	The duration for which the purchased EIP will use. The duration must be specified if the Billing Mode is set to Yearly/Monthly .	2 months
Auto-renew	Whether to select Auto-renew . You can select it if the Billing Mode is set to Yearly/Monthly . The auto-renewal period is determined by the required duration. <ul style="list-style-type: none">• Monthly subscription: The subscription is renewed every month.• Yearly subscription: The subscription is renewed each year.	N/A

3. Click **Next**.
4. Confirm the configurations.
 - If you set **Billing Mode** to **Pay-per-Use**, click **Submit**.
 - If you set **Billing Mode** to **Yearly/Monthly**, click **Pay Now**.
On the payment page, confirm the order information and click **Confirm**.

5.3 Adding EIPs to a Shared Bandwidth

Scenarios

You can add multiple EIPs to a shared bandwidth at the same time.

Notes and Constraints

- To add a yearly/monthly EIP to a shared bandwidth, you need to first change its billing mode to pay-per-use.
- If it is a premium shared bandwidth, you can add premium BGP EIPs and IPv6 NICs to it.

Procedure

1. Go to the [shared bandwidth list](#) page.
2. In the shared bandwidth list, locate the target shared bandwidth that you want to add EIPs to. In the **Operation** column, choose **Add Public IP Address**, and select the EIPs to be added.

NOTE

- After an EIP is added to a shared bandwidth, the dedicated bandwidth used by the EIP will become invalid and the EIP will start to use the shared bandwidth. The EIP's dedicated bandwidth will be deleted and will no longer be billed.
- An EIP cannot be configured for two shared bandwidths at the same time, so if you attempt to add an EIP to a second shared bandwidth, it will be automatically removed from the original shared bandwidth.

3. Click **OK**.

Helpful Links

[What Are the Differences Between a Dedicated Bandwidth and a Shared Bandwidth? Can a Dedicated Bandwidth Be Changed to a Shared Bandwidth or the Other Way Around?](#)

5.4 Removing EIPs from a Shared Bandwidth

Scenarios

Remove EIPs that are no longer required from a shared bandwidth if needed.

Notes and Constraints

A yearly/monthly EIP cannot be removed from a shared bandwidth purchased during OBT.

Procedure

1. Go to the [shared bandwidth list](#) page.
2. In the shared bandwidth list, locate the target shared bandwidth from which EIPs are to be removed, choose **More > Remove Public IP Address** in the **Operation** column, and select the EIPs to be removed in the displayed dialog box.
3. Set the EIP bandwidth after the EIP is removed. You can configure the EIP billing mode and bandwidth size.
4. Click **OK**.

5.5 Modifying a Shared Bandwidth

Scenarios

You can modify the name and size of a shared bandwidth as required.

- If a shared bandwidth is billed on a pay-per-use basis, the modification will take effect immediately. For details, see [Modifying a Shared Bandwidth \(Pay-per-Use\)](#).
- You can perform the following operations on a yearly/monthly shared bandwidth:
 - [Increasing a Shared Bandwidth \(Yearly/Monthly\)](#): The change will be applied immediately and the price difference will be billed accordingly.
 - [Decreasing a Shared Bandwidth \(Yearly/Monthly\) Immediately](#): The change will be applied immediately.
 - [Decreasing a Shared Bandwidth \(Yearly/Monthly\)](#): The change will be applied in the first billing cycle after a successful renewal.

If you want to change the billing mode of a shared bandwidth, see [How Do I Change My EIP Billing Mode from Pay-per-Use to Yearly/Monthly?](#)

Modifying a Shared Bandwidth (Pay-per-Use)

1. Go to the [shared bandwidth list](#) page.
2. In the shared bandwidth list, locate the row that contains the shared bandwidth you want to modify, click **Modify Bandwidth** in the **Operation** column, and modify the bandwidth settings.
3. Click **Next**.
4. Click **Submit**.
The modification takes effect immediately.

Increasing a Shared Bandwidth (Yearly/Monthly)

1. Go to the [shared bandwidth list](#) page.
2. In the shared bandwidth list, locate the row that contains the target shared bandwidth, and click **Modify Bandwidth** in the **Operation** column.
3. Select **Increase bandwidth** and click **Continue**.
4. In the **New Configuration** area on the **Modify Bandwidth** page, change the bandwidth name and size.
5. Click **Next**.
6. Confirm the information and click **Pay Now**.
After you complete the payment, the increased bandwidth will take effect immediately.

Decreasing a Shared Bandwidth (Yearly/Monthly) Immediately

1. Go to the [shared bandwidth list](#) page.
2. In the shared bandwidth list, locate the target shared bandwidth, and click **Modify Bandwidth** in the **Operation** column.
3. Select **Decrease bandwidth immediately** and click **Continue**.
4. In the **New Configuration** area on the **Modify Bandwidth** page, change the bandwidth name and size.
5. Click **Next**.
6. Confirm the information and click **Pay Now**.
After you complete the payment, the increased bandwidth will take effect immediately.

Decreasing a Shared Bandwidth (Yearly/Monthly)

1. Go to the [shared bandwidth list](#) page.
2. In the shared bandwidth list, locate the row that contains the target shared bandwidth, and click **Modify Bandwidth** in the **Operation** column.
3. Select **Decrease bandwidth** and click **Continue**.
4. In the **New Configuration** area on the **Modify Bandwidth** page, change the bandwidth name and size.

5. Click **Next**.
6. Confirm the information and click **Pay Now**.
After you complete the payment, the decreased bandwidth will take effect in the first billing cycle after the current subscription ends.

5.6 Deleting a Shared Bandwidth

Scenarios

Delete a shared bandwidth billed on a pay-per-use basis if it is no longer required.

Notes and Constraints

- A yearly/monthly shared bandwidth cannot be directly deleted. It can only be unsubscribed from.
- If you want to delete a shared bandwidth with EIPs added, you have to remove the EIPs from the shared bandwidth first.

Prerequisites

Before deleting a shared bandwidth, remove all the EIPs associated with it. For details, see [Removing EIPs from a Shared Bandwidth](#).

Procedure

1. Go to the [shared bandwidth list](#) page.
2. In the shared bandwidth list, locate the row that contains the pay-per-use shared bandwidth you want to delete, click **More** in the **Operation** column, and then click **Delete**.
3. In the displayed dialog box, click **OK**.

5.7 Exporting Shared Bandwidths

1. Go to the [shared bandwidth list](#) page.
2. On the shared bandwidth list page, select one or more shared bandwidths and click **Export** in the upper left corner.
The system will automatically export information about all of your shared bandwidths as an Excel file to a local directory.

6 Shared Data Package

6.1 Shared Data Package Overview

Shared data package provides a quota for data usage. Such packages are cost-effective and easy to use. Shared data packages take effect immediately after your purchase. If you have subscribed to pay-per-use EIPs billed by traffic in a region and buy a shared data package in the same region, the EIPs will use the shared data package. After the package quota is used up or the package expires, the EIPs will continue to be billed on a pay-per-use basis. For billing details, see [Product Pricing Details](#).

- Two types of packages are available: dynamic BGP and static BGP. Dynamic BGP data packages will be used by pay-per-use EIPs (billed by traffic) of the dynamic BGP type, and static BGP data packages will be used by pay-per-use EIPs (billed by traffic) of the static BGP type.
- Shared data packages can be purchased yearly or monthly. Packages purchased for a year are more cost effective. If you have multiple shared data packages, the data package with the shortest validity period will be used first.
- If your usage exceeds your shared data package quota within its validity, you will be billed on a pay-per-use basis for the additional traffic usage.
- If a shared data package expires, make sure your account balance is sufficient and your EIP will be billed on a pay-per-use basis.

Notes and Constraints

- Shared data packages require a one-off payment and take effect immediately after purchase. You cannot specify the effective date.
- Shared data packages cannot be unsubscribed from nor be modified once purchased and cannot be renewed upon expiration.
- Shared data packages are billed by month or year. Once expired, remaining package quota cannot be used anymore.
- Shared data packages can only be used by pay-per-use dedicated bandwidth billed by traffic. Two types of shared data packages are available: static BGP (for static BGP bandwidth) and dynamic BGP (for dynamic BGP bandwidth).
- A shared data package cannot be used for bandwidth of a specific EIP.

- A shared data package cannot be used for a shared bandwidth.
- A shared data package cannot be used by EIPs of the premium BGP type.

6.2 Buying a Shared Data Package

Scenarios

This section describes how to buy a shared data package. Shared data packages take effect immediately after your purchase. If you have subscribed to pay-per-use EIPs billed by traffic in a region and buy a shared data package in the same region, the EIPs will use the shared data package. After the package quota is used up or the package expires, the EIPs will continue to be billed on a pay-per-use basis.

Notes and Constraints

- Shared data packages require a one-off payment and take effect immediately after purchase. You cannot specify the effective date.
- Shared data packages cannot be unsubscribed from nor be modified once purchased and cannot be renewed upon expiration.
- Shared data packages are billed by month or year. Once expired, remaining package quota cannot be used anymore.
- Shared data packages can only be used by pay-per-use dedicated bandwidth billed by traffic. Two types of shared data packages are available: static BGP (for static BGP bandwidth) and dynamic BGP (for dynamic BGP bandwidth).
- A shared data package cannot be used for bandwidth of a specific EIP.
- A shared data package cannot be used for a shared bandwidth.
- A shared data package cannot be used by EIPs of the premium BGP type.
- If you have an order that has not been paid within the payment period, you need to cancel or pay for the order first. Then, you can purchase a shared data package.

Procedure

1. Go to the [Buy Shared Data Package](#) page.
2. Set the parameters as prompted.

Table 6-1 Parameter descriptions

Parameter	Description	Example Value
Region	A shared data package can only be used by resources in its same region. Select the region based on your requirements.	CN-Hong Kong

Parameter	Description	Example Value
Type	The shared data package type. Set this parameter based on the bandwidth type of the EIP. The following two types of packages are available: <ul style="list-style-type: none">• Dynamic BGP: A dynamic BGP data package can only be used by dynamic BGP EIPs billed by traffic on a pay-per-use basis.• Static BGP: A static BGP data package can only be used by static BGP EIPs billed by traffic on a pay-per-use basis.	Static BGP
Package Validity	The validity period of the shared data package. Select a validity period based on service requirements. A shared data package cannot be unsubscribed and takes effect immediately after you purchase it. Expired shared data packages will longer be available for use.	1 month
Specification	The size of the shared data package in GB.	10 GB
Usage Duration	The validity period of the shared data package.	Default

3. Click **Next**.
4. Confirm the configurations and click **Submit**.
5. On the payment page, confirm the order information and click **Confirm**.

6.3 Viewing the Usage Details and Configuring Remaining Usage Alerts

Scenarios

[Viewing the Usage of a Shared Data Package](#) and [Configuring Remaining Usage Alerts](#) are supported. After a remaining usage alert is configured, you can receive notifications via messages and emails once the remaining quota of a shared data package drops to a certain threshold in percentage.

This can remind you to purchase a new shared data package before the package you are currently using is used up, preventing high traffic fees from being generated. For example, if the size of your shared data package is 10 GB and the remaining usage threshold is 10%, notifications will be sent to you when the remaining quota in your shared data package is 1 GB.

Viewing the Usage of a Shared Data Package

1. Go to the [shared data package list](#) page.
2. In the **Usage/Total** column of the target shared data package, view the shared data usage and the total amount.

Configuring Remaining Usage Alerts

1. Log in to the management console.
2. Choose **Billing > My Packages**.
3. Click **Usage Alert** in the upper right corner to enable and configure the usage alert function for the corresponding package.
4. Click **OK**.

7 Global EIPs

7.1 Global EIP Overview

A global Elastic IP (global EIP) can be bound to a global connection bandwidth for private communication and to a global internet bandwidth for Internet access. You can specify a global region and a global EIP pool to assign a global EIP, and bind a global EIP to a cloud instance (such as ECS and load balancer) from any region. To enable an ECS to communicate with the Internet through a global EIP, you also need to bind a global internet gateway to the global EIP.

Figure 7-1 Global EIP architecture




Table 7-1 Global EIP communication scenarios

Communication Scenario	Required Resource	Description	Example	Operation Instruction
Intra-cloud communication	<ul style="list-style-type: none"> Global EIPs Global connection bandwidths Instances bound to global EIPs, such as ECSs and load balancers 	<p>To enable an instance to communicate on the cloud, the global EIP of the instance should have a global connection bandwidth bound. Select a global connection bandwidth type based on the global EIP access point and the region where the instance is located. Each global connection bandwidth can only be bound to one global EIP at a time.</p> <p>For details, see Global Private Connection Overview.</p>	<ul style="list-style-type: none"> The access point of global EIP-A is CN East-Hangzhou. The load balancer with global EIP-A bound is located in CN East-Shanghai1. CN East-Hangzhou and CN East-Shanghai1 are close to each other and belong to CN East. The type of the global connection bandwidth-A should be multi-city. The access point of global EIP-B is CN East-Hangzhou. The ECS-B with global EIP-B bound is located in CN South-Guangzhou. CN East-Hangzhou and CN South-Guangzhou are not close to each other but belong to the same geographic region. The type of the global connection bandwidth-B should be geographic-region. 	<ol style="list-style-type: none"> Assigning a Global EIP Binding a Global EIP to an Instance: Each global EIP can only be bound to one instance at a time. Adding Instances to a Global Connection Bandwidth: Each global connection bandwidth can only be used by one global EIP at a time.

Communication Scenario	Required Resource	Description	Example	Operation Instruction
			<ul style="list-style-type: none"> The access point of global EIP-C is CN East-Hangzhou. The ECS-C with global EIP-C bound is located in CN-Hong Kong. CN East-Hangzhou and CN-Hong Kong belong to different geographic regions. The type of the global connection bandwidth-C should be cross-geographic-region. 	
Internet communication	<ul style="list-style-type: none"> Global EIPs Global internet bandwidth Instances bound to global EIPs, such as ECSs and load balancers 	<p>To enable an instance to communicate with the Internet, the global EIP of the instance should have a global internet bandwidth bound. The global EIP and the global internet bandwidth must have the same access point. Multiple global EIPs can be added to the same global internet bandwidth. For details, see Overview.</p>	<p>Global EIP-A, global EIP-B, and global EIP-C are added to global internet bandwidth-A. The global EIPs and the global internet bandwidth use the same access point, that is, CN East-Hangzhou.</p>	<ol style="list-style-type: none"> Buying a Global Internet Bandwidth Adding Global EIPs to a Global Internet Bandwidth

Global EIP Quotas

You can log in to the console to query your global EIP quotas.

If you want to increase your quota, see [How Do I Apply for a Higher Quota?](#)

- Your request for a larger quota will only be approved if your account has valid orders and you are continuously using cloud resources. If you have released resources immediately after subscribing to them multiple times, your request for quota increase will be declined.
- If you have increased the global EIP quota but you have not used the quota for a long time, Huawei Cloud will reduce the quota to the default value.

Notes and Constraints

- Global EIPs cannot be used independently. You need to bind them to cloud instances, such as ECSs and load balancers. For details, see [Binding a Global EIP to an Instance](#).
- After a global EIP is bound to an instance, you need to bind a global connection bandwidth to the global EIP. For details, see [Adding Instances to a Global Connection Bandwidth](#).

7.2 Assigning a Global EIP

Scenarios

This section describes how to assign a global EIP. You can specify the access point, type, and global EIP pool based on your service requirements. Global EIPs can be bound to cloud instances (such as ECSs or load balancers) from any region.

If you want to assign a global EIP, [submit a service ticket](#).

Procedure

1. Go to the [Assign Global EIP](#) page.
2. Configure the parameters based on [Table 7-2](#).

Table 7-2 Parameter descriptions

Parameter	Description	Example Value
Region	Mandatory A global EIP can only be added to a global internet bandwidth from its same region. For details about regions, see Selecting a Region .	CN East-Shanghai1
City	Mandatory A global internet bandwidth can only be shared by global EIPs from its same city.	Shanghai

Parameter	Description	Example Value
Type	Select Global EIP or Global EIP range .	Global EIP
Version	Select IPv4 or IPv6 .	IPv4
Global EIP Type	Mandatory <ul style="list-style-type: none">Dynamic BGP is supported by default.After you select a global EIP pool, the system will allocate a global EIP to you from the pool. Select a resource pool close to your business to minimize the latency.	-
Global Internet Bandwidth	Mandatory <ul style="list-style-type: none">Assign now: Select this option if you want to purchase a new global internet bandwidth.Use existing: Select this option if you want to add the global EIP to an existing global internet bandwidth for internet access.	-
Billing Mode	Pay-per-use is selected by default.	Pay-per-use
Bandwidth Type	The bandwidth type. Standard is selected by default.	Standard
Billed By	You can select: <ul style="list-style-type: none">95th percentile bandwidth (standard)	95th percentile bandwidth (standard)
Guaranteed Bandwidth	The system automatically generates the guaranteed bandwidth percentage based on what you select for Billed By .	0%
Bandwidth (Mbit/s)	The bandwidth size in Mbit/s.	300
Global EIP Name	Optional Enter the name of the global EIP. The name: <ul style="list-style-type: none">Must contain 0 to 64 characters.Can contain letters, digits, underscores (_), hyphens (-), and periods (.).	geip-test

Parameter	Description	Example Value
Enterprise Project	<p>The enterprise project that the global EIP belongs to.</p> <p>An enterprise project facilitates project-level management and grouping of cloud resources and users. The default project is default.</p> <p>For details about creating and managing enterprise projects, see the Enterprise Management User Guide.</p>	default
Advanced Settings	Click the drop-down arrow to configure parameters, including the bandwidth name and tag.	Retain the default settings.
Bandwidth Name	<p>Optional</p> <p>Enter the name of the bandwidth. The name:</p> <ul style="list-style-type: none">• Must contain 0 to 64 characters.• Can contain letters, digits, underscores (_), hyphens (-), and periods (.).	ibw-test
Tag	<p>Global EIP tag, which consists of a key and value pair.</p> <p>The tag key and value must meet the requirements listed in Table 7-3.</p>	<ul style="list-style-type: none">• Key: geip_1• Value: 184.100.101.102
Monitoring	<p>This function is free. With Cloud Eye, you can monitor:</p> <ul style="list-style-type: none">• Network traffic at one-minute intervals.• Bandwidth fluctuations and inbound and outbound bandwidth rates.	-
Quantity	Number of global EIPs to be assigned.	3

Table 7-3 Naming rules for global EIP tags

Parameter	Requirement	Example Value
Key	<ul style="list-style-type: none">• Cannot be left blank.• Must be unique for a global EIP.• Can contain a maximum of 36 characters.• Can contain letters, digits, underscores (_), and hyphens (-).	geip_1
Value	<ul style="list-style-type: none">• Can contain a maximum of 43 characters.• Can contain letters, digits, underscores (_), periods (.), and hyphens (-).	184.100.101.102

3. Click **Next**.
4. Confirm the configurations and click **Submit**.
The global EIP list is displayed.
5. In the global EIP list, view the global EIP status.
If the status of the global EIP is **Unbound**, the EIP is assigned successfully.

Follow-Up Procedure

- (Mandatory) Global EIPs cannot be used independently. You need to bind them to cloud instances, such as ECSs and load balancers. For details, see [Binding a Global EIP to an Instance](#).
- (Mandatory) After a global EIP is bound to an instance, you need to bind a global connection bandwidth to the global EIP. For details, see [Adding Instances to a Global Connection Bandwidth](#).

7.3 Binding a Global EIP to an Instance

Scenarios

This section describes how to bind a global EIP to an instance, such as an ECS or a load balancer, to enable the instance to communicate with the Internet through the global EIP.

NOTE

By default, a global EIP can be bound to instances in the same geographic region. To bind a global EIP to an instance in another geographic region, [submit a service ticket](#).

Notes and Constraints

- A global EIP can be bound to only one instance at a time.
- After a global EIP is bound to an ECS, the VPC of the ECS cannot be changed, and no more EIP can be bound to the ECS.
- A global EIP cannot be bound to a shared load balancer.

Prerequisites

- The required instance (such as ECS or ELB) has been created.
- For an ECS, you also need to create a global internet gateway for the VPC that the ECS belongs to.

Procedure

1. Go to the [global EIP list page](#).
2. In the global EIP list, search for or locate the target global EIP.
3. Locate the target global EIP, and click **Bind Instance** in the **Progress** column. The page for binding an instance is displayed.
4. Select the region that the instance to be bound is located. A global EIP can be bound to an instance in any region.
5. Select the type of the instance to be bound and then select the instance.
6. Select the global internet gateway to be bound. The system automatically lists the global internet gateway of the VPC that the instance belongs to, if there is one.
7. Click **Next**.
8. Configure **Global Connection Bandwidth**, **Bandwidth Name**, and **Bandwidth** as prompted.
9. Click **OK**. In the global EIP list, you can see that the global EIP has instance bound.

Related Operations

- (Mandatory) After a global EIP is bound to an instance, you need to bind a global connection bandwidth to the global EIP. For details, see [Adding Instances to a Global Connection Bandwidth](#).
- You need to create a global internet gateway for the VPC of the ECS. For details, see [Creating a Global Internet Gateway](#).

7.4 Unbinding a Global EIP from an Instance

Scenarios

This section describes how to unbind a global EIP from an instance, for example, from ECS or load balancer.

Notes

- When you unbind a global EIP from an instance, the system automatically unbinds the global connection bandwidth from the global EIP. Ensure that no service is running on the instance. Otherwise, services will be interrupted.
- A global EIP can be bound to only one instance at a time. If you need to bind the global EIP to another instance, unbind it from the current instance first and then bind it to another one. For details, see [Binding a Global EIP to an Instance](#).

Procedure

1. Go to the [global EIP list page](#).
2. In the global EIP list, search for or locate the target global EIP.
3. Locate the row that contains the target global EIP, and click **Unbind** in the **Operation** column.
A confirmation dialog box is displayed.
4. Click **OK**.
In the global EIP list, you can see that the global EIP has no instance bound.

7.5 Viewing Details About a Global EIP

Scenarios

This section describes how to view details about a global EIP, including its status, global internet bandwidth, and global connection bandwidth.

Procedure

1. Go to the [global EIP list page](#).
2. In the list, search for or locate the global EIP.

7.6 Releasing a Global EIP

Scenarios

This section describes how to release a global EIP.

If your global EIPs are no longer required, release them by following the instructions provided in this section.

Notes and Constraints

If you want to release a global EIP with an instance bound, you need to unbind it from its instance first by referring to [Unbinding a Global EIP from an Instance](#).

Procedure

1. Go to the [global EIP list page](#).

2. In the global EIP list, search for or locate the target global EIP.
3. In the list, search for or locate the global EIP.
4. Locate the row that contains the target global EIP, and click **Release** in the **Operation** column.
A confirmation dialog box is displayed.
5. Confirm the information and click **OK**.
The released global EIP is not displayed in the global EIP list.

7.7 Modifying the Global Connection Bandwidth of a Global EIP

Scenarios

This section describes how to modify the name or change the size of a global connection bandwidth.

Your increased or decreased global connection bandwidth takes effect immediately.

Procedure

1. Go to the [global EIP list page](#).
2. In the global EIP list, search for or locate the target global EIP.
3. Locate the row that contains the target global EIP, and choose **More > Modify Global Connection Bandwidth** in the **Operation** column.
The **Modify Global Connection Bandwidth** page is displayed.
4. Locate the target bandwidth and choose **More > Modify Bandwidth** in the **Operation** column.
5. Modify the bandwidth name and size as prompted, and click **Next**.
6. Confirm the modified information and click **Submit**.

7.8 Modifying the Global Internet Bandwidth of a Global EIP

Scenarios

This section describes how to modify the name, billing option, or size of a global internet bandwidth.

Your increased or decreased global internet bandwidth takes effect immediately.

Procedure

1. Go to the [global EIP list page](#).
2. In the global EIP list, search for or locate the target global EIP.

3. Locate the row that contains the target global EIP, and choose **More > Modify Global Internet Bandwidth** in the **Operation** column.

The **Modify Global Internet Bandwidth** page is displayed.

4. Modify the bandwidth parameters as required.
5. Click **Next**.
6. Confirm the configurations and click **Submit**.

The modified bandwidth is displayed in the global internet bandwidth list.

8 Global Internet Gateways

8.1 Global Internet Gateway Overview


After a global EIP is bound to an ECS, a global internet gateway is required to connect the VPC of the ECS to the global EIP so that the ECS can access the Internet through the global EIP. Before binding an ECS, you need to create a global internet gateway. Global internet gateways are free of charge.

When you bind a global internet gateway to a global EIP of an ECS, the system automatically lists the global internet gateway of the VPC that the ECS belongs to, if there is one.

NOTE

- If a global EIP is bound to a load balancer, you do not need to create a global internet gateway for the VPC that the load balancer belongs to.

Figure 8-1 Global EIP architecture



Notes and Constraints

- Each VPC can only have one global internet gateway attached.
- After a global internet gateway is purchased, you cannot modify parameters such as subnet and more. If you want your global internet gateway to work in another subnet, delete it and create another global internet gateway.

8.2 Creating a Global Internet Gateway

Scenarios

This section describes how to create a global internet gateway. A global internet gateway is used to connect the VPC where an ECS resides to the global EIP of the ECS. Global internet gateways are free of charge.

Notes and Constraints

Each VPC can only have one global internet gateway attached.

Procedure

1. Go to the [global internet gateway list](#) page.
2. In the upper right corner of the page, click **Create Global Internet Gateway**. The **Create Global Internet Gateway** is displayed.
3. Configure the parameters based on [Table 8-1](#).

Table 8-1 Parameter descriptions

Parameter	Description	Example Value
Name	Mandatory Enter the name of the global internet gateway. The name: <ul style="list-style-type: none">• Must contain 1 to 64 characters.• Can contain letters, digits, underscores (_), hyphens (-), and periods (.).	igw-89ad
Version	<ul style="list-style-type: none">• IPv4: Mandatory• IPv6: Optional	IPv4
VPC	Mandatory Select the VPC of your instance (such as ECS) that needs to communicate with the Internet to attach the global internet gateway. A global internet gateway is used work together with the global EIP of your instance for Internet access.	-
Subnet	Mandatory Select the subnet where you want to bound the global internet gateway.	-
Default Route	Optional <ul style="list-style-type: none">• If you select this option, the default route with the destination 0.0.0.0/0 will be automatically added to the default route table of the selected VPC to direct traffic to the global internet gateway.• If you do not select this option, you need to manually add a route to the route table (default or custom) associated with the VPC subnet of your ECS to direct traffic to the global internet gateway. NOTICE If an error is reported when you select this option, this indicates that the default route with the destination 0.0.0.0/0 already exists in the default route table of the VPC. You can manually add a route to the route table (default or custom) associated with the VPC subnet of your ECS to direct traffic to the global internet gateway.	-

4. Click **OK**.

8.3 Deleting a Global Internet Gateway

Scenarios

This section describes how to delete a global internet gateway.

Notes and Constraints

A global internet gateway cannot be deleted if its attached VPC has instances (such as ECSs) with global EIPs bound. To delete such a global internet gateway, unbind the global EIPs from the instances first by referring to [Unbinding a Global EIP from an Instance](#).

Procedure

1. Go to the [global internet gateway list](#) page.
2. In the global internet gateway list, search for the target global internet gateway.
3. Locate the row that contains the target global internet gateway and click **Delete** in the **Operation** column.
A confirmation dialog box is displayed.
4. Click **OK**.

8.4 Modifying a Global Internet Gateway

Scenarios

This section describes how you can change the name of a global internet gateway and enable IPv6.

Notes and Constraints

You cannot modify parameters such as subnet and more. If you want your global internet gateway to work in another subnet, delete it and create another global internet gateway.

Procedure

1. Go to the [global internet gateway list](#) page.
2. In the global internet gateway list, search for or locate the target global internet gateway.
3. Change the name of the global internet gateway.
 - a. Click the edit icon on the right of the target global internet gateway name. The **Edit Global Internet Gateway Name** dialog box displays.
 - b. Enter a new name for the global internet gateway and click **OK**.

8.5 Binding a Global Internet Gateway to a Global EIP

Scenarios

This section describes how to bind a global internet gateway to a global EIP. When you bind a global internet gateway to a global EIP of an ECS, the system automatically lists the global internet gateway of the VPC that the ECS belongs to, if there is one.

Prerequisites

A global internet gateway has been created for the VPC of the ECS. If there is no global internet gateway, create one by referring to [Creating a Global Internet Gateway](#).

Procedure

1. Go to the [global EIP list page](#).
2. In the global EIP list, search for or locate the target global EIP.
3. Locate the target global EIP, and click **Bind Instance** in the **Progress** column.
The page for binding an instance is displayed.
4. Select the region that the instance to be bound is located.
A global EIP can be bound to an instance in any region.
5. Select the type of the instance to be bound and then select the instance.
6. Select the global internet gateway to be bound.
7. Click **OK**.

8.6 Unbinding a Global Internet Gateway from a Global EIP

Scenarios

This section describes how to unbind a global internet gateway from a global EIP. When you unbind a global EIP from an ECS, the system automatically unbinds the global internet gateway of the VPC that ECS belongs to from the global EIP.

Procedure

1. Go to the [global EIP list page](#).
2. In the global EIP list, search for or locate the target global EIP.
3. Locate the row that contains the target global EIP, and click **Unbind** in the **Operation** column.
A confirmation dialog box is displayed.
4. Click **OK**.

In the global EIP list, you can see that the global EIP has no instance bound.

9 Global Internet Bandwidths


9.1 Overview

A global internet bandwidth can be shared by one or more global EIPs at the same time, improving bandwidth utilization.

Global internet bandwidths have to work together with global EIPs for Internet access. You can add one or more global EIPs to the same global internet bandwidth. A global EIP and its global internet bandwidth must use the same access point. [Figure 9-1](#) shows the architecture.

Global EIP-A, global EIP-B, and global EIP-C are added to global internet bandwidth-A. The global EIPs and the global internet bandwidth use the same access point, that is, CN East-Hangzhou.

Figure 9-1 Global EIP architecture



Notes and Constraints

- The global EIPs must have the same access information, including geographic region, geographic area, access point, and type, as their global internet bandwidth.
- A global EIP to be removed from a global internet bandwidth cannot have an instance bound. If there is an instance, unbind the global EIP from its instance first by referring to [Unbinding a Global EIP from an Instance](#).
- To unbind a global EIP from an instance, ensure that there are no services running on the instance. Otherwise, services will be interrupted.
- A global internet bandwidth to be deleted cannot have any global EIP associated.

9.2 Buying a Global Internet Bandwidth

Scenarios

This section describes how to buy a global internet bandwidth.

Procedure

1. Go to the [Buy Global Internet Bandwidth](#) page.
2. Configure the parameters based on [Table 9-1](#).

Table 9-1 Parameter descriptions

Parameter	Description	Example Value
Billing Mode	The billing mode of the global internet bandwidth. You can select Pay-per-use .	Pay-per-use
Region	Mandatory A global internet bandwidth can only be shared by global EIPs from its same region. For details about regions, see Selecting a Region .	CN East-Shanghai1
City	Mandatory A global internet bandwidth can only be shared by global EIPs from its same city.	Shanghai
Type	Mandatory Dynamic BGP is supported by default.	-
Bandwidth Type	The bandwidth type can be Standard .	Standard
Billed By	You can select: 95th percentile bandwidth (standard)	95th percentile bandwidth (standard)
Guaranteed Bandwidth	The system automatically generates the guaranteed bandwidth percentage based on what you select for Billed By .	20%
Bandwidth (Mbit/s)	Mandatory Select the size of the bandwidth. The unit is Mbit/s.	100
Global Internet Bandwidth Name	Optional Enter the name of the bandwidth. The name: <ul style="list-style-type: none">• Must contain 0 to 64 characters.• Can contain letters, digits, underscores (_), hyphens (-), and periods (.).	ibw-test
Enterprise Project	The enterprise project that the global internet bandwidth belongs to. An enterprise project facilitates project-level management and grouping of cloud resources and users. The default project is default . For details about creating and managing enterprise projects, see the Enterprise Management User Guide .	default

Parameter	Description	Example Value
Tag	Global internet bandwidth tag, which consists of a key and value pair. The tag key and value must meet the requirements listed in Table 9-2 .	<ul style="list-style-type: none">• Key: geip_1.1• Value: 10
Description	Supplementary information about the global internet bandwidth. This parameter is optional.	-

Table 9-2 Tag naming rules

Parameter	Requirement	Example Value
Key	<ul style="list-style-type: none">• Cannot be left blank.• Must be unique for a global internet bandwidth.• Can contain a maximum of 36 characters.• Can contain letters, digits, underscores (_), and hyphens (-).	geip_1.1
Value	<ul style="list-style-type: none">• Can contain a maximum of 43 characters.• Can contain letters, digits, underscores (_), periods (.), and hyphens (-).	10

3. Click **Next**.
4. Confirm the configurations and click **Submit**.
The global internet bandwidth list page is displayed.
5. In the global internet bandwidth list, view the status of the bandwidth.
If the status of the bandwidth is **Normal**, the purchase is successful.

Follow-Up Procedure

If your instance with a global EIP bound needs to access the Internet, you also need to add the global EIP to a global internet bandwidth. For details, see [Adding Global EIPs to a Global Internet Bandwidth](#).

9.3 Adding Global EIPs to a Global Internet Bandwidth

Scenarios

This section describes how to add global EIPs to a global internet bandwidth. Only after this, the instances with the global EIPs bound can access the Internet.

Notes and Constraints

- You can add multiple global EIPs to a global internet bandwidth.
- The global EIPs must have the same access information, including geographic region, geographic area, access point, and type, as their global internet bandwidth.

Procedure

1. Go to the [global internet bandwidth list page](#).
2. In the global internet bandwidth list, search for or locate the target bandwidth.
3. You can use either of the following methods to add a global EIP to a global internet bandwidth:
 - Method 1:
 - i. In the global internet bandwidth list, locate the row that contains the target global internet bandwidth, and click **Add Global EIP** in the **Operation** column.
The **Add Global EIP** page is displayed.
 - ii. Select one or more global EIPs and click **OK**.
In the global internet bandwidth list, the number of global EIPs of the bandwidth increased.
 - Method 2:
 - i. In the global internet bandwidth list, click the name of the target global internet bandwidth.
The **Basic Information** tab page is displayed.
 - ii. Click the **Global EIPs** tab and then click **Add**.
The **Add Global EIP** page is displayed.
 - iii. Select one or more global EIPs and click **OK**.
The selected global EIPs are displayed on the global EIP list.

9.4 Modifying a Global Internet Bandwidth

Scenarios

This section describes how to modify the name, billing option, or size of a global internet bandwidth.

Your increased or decreased global internet bandwidth takes effect immediately.

Procedure

1. Go to the [global internet bandwidth list page](#).
2. In the global internet bandwidth list, search for or locate the target bandwidth.
3. Locate the row that contains the target bandwidth, and click **Modify Bandwidth** in the **Operation** column.

The **Modify Global Internet Bandwidth** page is displayed.

4. Modify the bandwidth parameters as required.
5. Click **Next**.
6. Confirm the configurations and click **Submit**.

The modified bandwidth is displayed in the global internet bandwidth list.

9.5 Viewing a Global Internet Bandwidth

Scenarios

This section describes how to view the details about a global internet bandwidth, including the bandwidth name, size, and creation time.

Procedure

1. Go to the [global internet bandwidth list page](#).
2. In the global internet bandwidth list, search for or locate the target bandwidth.
3. Click the name of the target global internet bandwidth.

Go to the **Basic Information** tab page to view more information.

9.6 Deleting a Global Internet Bandwidth

Scenarios

This section describes how to delete a global internet bandwidth.

Notes and Constraints

A global internet bandwidth to be deleted cannot have any global EIP associated.

Procedure

1. Go to the [global internet bandwidth list page](#).
2. In the global internet bandwidth list, search for or locate the target bandwidth.
3. Locate the row that contains the target bandwidth, and click **Delete** in the **Operation** column.

A confirmation dialog box is displayed.

4. Click **OK**.

The deleted bandwidth is not displayed in the global internet bandwidth list.

10 Global Connection Bandwidths

10.1 Overview

A global connection bandwidth is used by instances to allow communication over the backbone network.

NOTE

- In Cloud Connect, global connection bandwidths are mainly used by central networks.
- By default, global connection bandwidths cannot be used by cloud connections. Only some existing users can bind global connection bandwidths to cloud connections.

There are different types of global connection bandwidths that are designed for different application scenarios, including multi-city, geographic-region, and cross-geographic-region bandwidths. Geographic-region and cross-geographic-region bandwidths are often bound to cloud connections for communication on the cloud.

Table 10-1 Global connection bandwidth types

Bandwidth Type	Instance Type	Description	Scenario
Multi-city	Global EIPs	Select this type of bandwidth if you need communication between cloud regions in the same region, for example, CN East-Shanghai1 and CN East-Shanghai2 in East China.	A global EIP and its associated resource, such as an ECS or load balancer, have to be in the same region. Multi-city Bandwidth Application Scenario (Global EIP)


Bandwidth Type	Instance Type	Description	Scenario
Geographic - region	<ul style="list-style-type: none"> Global EIPs Cloud connection 	Select this type of bandwidth if you need communication within a geographic region. Geographic regions include the Chinese mainland, Asia Pacific, and Southern Africa. For example, CN East-Shanghai1 and CN South-Guangzhou are regions in the Chinese mainland. For details about the relationship between geographic regions and Huawei Cloud regions, see Geographic Regions and Huawei Cloud Regions .	<ul style="list-style-type: none"> A global EIP and its associated resource, such as an ECS or load balancer, have to be in the same geographic region. Geographic-Region Bandwidth Application Scenario (Global EIP) Enterprise routers on a central network are from the same geographic region. Geographic-Region or Cross-Geographic-Region Bandwidth Application Scenario (Central Network)
Cross-geographic - region	<ul style="list-style-type: none"> Global EIPs Cloud connection 	Select this type of bandwidth if you need communication across geographic regions. Geographic regions include the Chinese mainland, Asia Pacific, and Southern Africa. For example, CN East-Shanghai1 and CN-Hong Kong are from different geographic regions. For details about the relationship between geographic regions and Huawei Cloud regions, see Geographic Regions and Huawei Cloud Regions .	<ul style="list-style-type: none"> A global EIP and its associated resource, such as an ECS or load balancer, are from different geographic regions. Cross-Geographic-Region Bandwidth Application Scenario (Global EIP) Enterprise routers on a central network are from different geographic regions. Geographic-Region or Cross-Geographic-Region Bandwidth Application Scenario (Central Network)

Multi-city Bandwidth Application Scenario (Global EIP)

In this example, a global EIP is bound to an ECS.

The ECS is in the CN East-Shanghai1 region, and the access point of the global EIP is in Hangzhou, a city in East China.

Figure 10-1 Multi-city bandwidth application scenario (global EIP)




Geographic-Region Bandwidth Application Scenario (Global EIP)

In this example, a global EIP is bound to an ECS.

The ECS is in the CN South-Guangzhou region, and the access point of the global EIP is in Hangzhou. Both Guangzhou and Hangzhou are cities on the Chinese mainland.

Figure 10-2 Geographic-region bandwidth application scenario (global EIP)



Cross-Geographic-Region Bandwidth Application Scenario (Global EIP)


In this example, a global EIP is bound to an ECS.

The ECS is in the CN-Hong Kong region, and the access point of the global EIP is in Hangzhou. CN-Hong Kong is a cloud region in Asia Pacific, but Hangzhou is a city on the Chinese mainland.

- Geographic region 1: Asia Pacific, the geographic region where the ECS is located
- Geographic region 2: Chinese mainland, the geographic region where the global EIP is accessed

NOTE


Ensure that the geographic regions 1 and 2 are configured as above.

Figure 10-3 Cross-geographic-region bandwidth application scenario (global EIP)

Geographic-Region or Cross-Geographic-Region Bandwidth Application Scenario (Central Network)

In this example, enterprise routers are connected over a cloud connection.

- Enterprise router 1 in CN East-Shanghai1 and enterprise router 2 in CN South-Guangzhou are from the same geographic region. A geographic-region bandwidth can be used for communication between the two enterprise routers.
 - Enterprise router 1 in CN East-Shanghai1 and enterprise router 3 in CN-Hong Kong are in different geographic regions. A cross-geographic-region bandwidth can be used for communication between the two enterprise routers.
 - Geographic region 1: Chinese mainland, geographic region where enterprise router 1 is located
 - Geographic region 2: Asia Pacific, geographic region where enterprise router 3 is located
- NOTE**
- Ensure that both the geographic regions of enterprise router 1 and enterprise router 3 have been configured.
- Enterprise router 2 in CN South-Guangzhou and enterprise router 3 in CN-Hong Kong are in different geographic regions. A cross-geographic-region bandwidth can be used for communication between the two enterprise routers.
 - Geographic region 1: Chinese mainland, geographic region where enterprise router 2 is located
 - Geographic region 2: Asia Pacific, geographic region where enterprise router 3 is located

Figure 10-4 Geographic-region or cross-geographic-region bandwidth application scenario (central network)

10.2 Buying a Global Connection Bandwidth

Scenarios

This section describes how to buy a global connection bandwidth for communication over the backbone network.

Procedure

1. Go to the [Buy Global Connection Bandwidth](#) page.
2. Configure the parameters based on [Table 10-2](#).

Table 10-2 Parameters required for buying a global connection bandwidth

Parameter	Description
Billing Mode	<p>Mandatory</p> <p>Pay-per-use: a postpaid subscription. You are charged based on the usage duration of the global connection bandwidth. Your global connection bandwidth is billed by second, and you are charged for a minimum of 60 seconds each time. If the usage is less than an hour, you are charged based on the actual duration, accurate to seconds.</p>
Bandwidth Type	<p>Mandatory</p> <p>There are different types of global connection bandwidths that are designed for different application scenarios, including multi-city, geographic-region, and cross-geographic-region bandwidths. The type of a bandwidth cannot be changed after your purchase.</p> <p>Select a bandwidth type. For details, see Global Connection Bandwidth Overview.</p> <p>You can decide whether to use a geographic-region bandwidth or cross-geographic-region bandwidth based on service scenarios.</p> <p>If you select a geographic-region bandwidth or cross-geographic-region bandwidth, you also need to select geographic region(s) and specify the regions that need to communicate with each other.</p>
Billed By	<p>Mandatory</p> <p>The price of a global connection bandwidth varies by its size.</p> <ul style="list-style-type: none">• After a bandwidth is purchased, the billing starts immediately regardless of whether the bandwidth is used.• If a bandwidth is no longer required, delete it in a timely manner to avoid unnecessary fees.
Bandwidth	<p>Mandatory</p> <p>Select the bandwidth, in Mbit/s.</p>
Bandwidth Name	<p>Mandatory</p> <p>Enter the name of the bandwidth. The name:</p> <ul style="list-style-type: none">• Must contain 1 to 64 characters.• Can contain letters, digits, underscores (_), hyphens (-), and periods (.).
Enterprise Project	<p>Mandatory</p> <p>Provides a cloud resource management mode, in which cloud resources and members are centrally managed by project.</p>

Parameter	Description
Bandwidth Type	<p>Mandatory</p> <p>There are different types of global connection bandwidths that are designed for different application scenarios, including multi-city, geographic-region, and cross-geographic-region bandwidths. The type of a bandwidth cannot be changed it is created.</p> <p>If you plan to bind this bandwidth to a cloud connection, you can select a geographic-region bandwidth or cross-geographic-region bandwidth.</p> <p>If you select a geographic-region bandwidth or cross-geographic-region bandwidth, you also need to select geographic region(s) and specify the regions that need to communicate with each other.</p>
Billed By	<p>Mandatory</p> <p>The price of a global connection bandwidth varies by its size.</p> <ul style="list-style-type: none">• After a bandwidth is purchased, the billing starts immediately regardless of whether the bandwidth is used.• If a bandwidth is no longer required, delete it in a timely manner to avoid unnecessary fees.
Bandwidth	<p>Mandatory</p> <p>Select the bandwidth, in Mbit/s.</p>
Bandwidth Name	<p>Mandatory</p> <p>Enter the name of the bandwidth. The name:</p> <ul style="list-style-type: none">• Must contain 1 to 64 characters.• Can contain letters, digits, underscores (_), hyphens (-), and periods (.).
Enterprise Project	<p>Mandatory</p> <p>Provides a cloud resource management mode, in which cloud resources and members are centrally managed by project.</p>

3. Click **Next**.
4. Confirm the configurations and click **Submit**.
The global connection bandwidth list page is displayed.
5. In the global connection bandwidth list, view the status of the bandwidth.
If the bandwidth status becomes **Normal**, the purchase is successful.

10.3 Adding Instances to a Global Connection Bandwidth

Scenarios

Central networks and global EIPs can use global connection bandwidths for communication.

Constraints

- Instances that can be added to a global connection bandwidth must be from the same region as the bandwidth.
- A global connection bandwidth can only be used by instances of the same type. If you want another type of instances to use a global connection bandwidth that already has instances, you need to remove the instances first.
 - You can add or remove global EIPs in batches.
 - You can bind one global connection bandwidth to or unbind it from a central network at a time.
- To use a global connection bandwidth on a central network, you need to configure cross-site connections by referring to the following:
 - [Creating a central network](#)
 - [Applying a policy](#)
 - [Managing attachments](#)
- Global connection bandwidths of different types can be used with different instances. For details, see the following table.

Table 10-3 Instances that can use a global connection bandwidth

Bandwidth Type	Global EIP	Central Network
Multi-city	√	×
Geographic-region	√	√
Cross-geographic-region	√	√

Using a Global Connection Bandwidth on a Central Network

1. Go to the [Central Networks](#) page.
2. Locate the central network and click its name.
3. Click the **Cross-Site Connection Bandwidths** tab.
4. Locate the cross-site connection and click **Assign** in the **Global Connection Bandwidth** column.
5. On the **Assign Cross-Site Connection Bandwidth** page, select the global connection bandwidth.

6. Specify the bandwidth and click **OK**.

Adding Global EIPs to a Global Connection Bandwidth

1. Go to the [Global Connection Bandwidths](#) page.
2. Locate the global connection bandwidth and click **Bind** in the **Operation** column.
3. In the displayed dialog box, select **Global EIP** for **Instance Type**.
For a multi-city global connection bandwidth, select the two regions where the bandwidth will be used.
4. Search for global EIPs using keyword.
5. Select one or more global EIPs and click **OK**.

10.4 Removing Instances from a Global Connection Bandwidth


Scenarios

You can remove global EIPs from a global connection bandwidth or unbind a global connection bandwidth from a central network.

Constraints

- Before an instance is removed from a global connection bandwidth, the instance is not used to run workloads or establish network connectivity, or the workloads will be unavailable or the network will be interrupted.
- A global connection bandwidth can only be used by one type of instances. If you want to change the instance type, remove all the instances from the global connection bandwidth and then add instances of another type by referring to [Adding Instances to a Global Connection Bandwidth](#).
- If cross-site connection bandwidths have been assigned from a global connection bandwidth, the global connection bandwidth cannot be unbound from the cloud connection. You need to delete the cross-site connection bandwidths first.

Deleting Cross-Site Connection Bandwidth

1. Click  in the upper left corner to select a region and a project.
2. Go to the [Central Networks](#) page.
3. Locate the central network and click its name.
4. Click the **Cross-Site Connection Bandwidths** tab.
5. Locate the cross-site connection and click **Delete Bandwidth** in the **Operation** column.
6. In the displayed dialog box, click **OK**.

Removing Instances from a Global Connection Bandwidth

1. Go to the [Global Connection Bandwidths](#) page.
2. Locate the global connection bandwidth and click **Unbind** in the **Operation** column.
 - If the bandwidth is only bound to one instance, click **Remove** in the **Operation** column and then click **OK** in the displayed dialog box.
 - If the bandwidth is bound to more than one instance:
 - i. On the details page of the bandwidth, click **Associated Instances**.
 - ii. Select the instances.
 - iii. Click **Remove** above the instance list.
 - iv. In the displayed dialog box, click **OK**.

10.5 Managing a Global Connection Bandwidth

Scenarios


This section describes how to modify or delete a global connection bandwidth.

You can only modify the bandwidth name and bandwidth. If you modify the bandwidth, the new bandwidth takes effect immediately.


Constraints

If a global connection bandwidth is in use by instances, it cannot be deleted. Remove the instances from the global connection bandwidth first. For details, see [Removing Instances from a Global Connection Bandwidth](#).

Modifying a Global Connection Bandwidth

1. Click  in the upper left corner to select a region and a project.
2. Go to the [Global Connection Bandwidths](#) page.
3. Locate the global connection bandwidth you want to modify and choose **More > Modify Bandwidth** in the **Operation** column.
4. On the **Modify Global Connection Bandwidth** page, modify the bandwidth name and bandwidth and click **Next**.
5. Confirm the information and click **Submit**.

Deleting a Global Connection Bandwidth

1. Click  in the upper left corner to select a region and a project.
2. Go to the [Global Connection Bandwidths](#) page.
3. Locate the global connection bandwidth you want to delete and choose **More > Delete** in the **Operation** column.
4. In the displayed dialog box, click **OK**.

11 Cloud Eye Monitoring

11.1 Supported Metrics

Description

This section describes the namespace, list, and measurement dimensions of metrics of EIPs and bandwidths that you can check on Cloud Eye. You can use APIs or the Cloud Eye console to query the metrics of the monitored metrics and generated alarms.

Namespace

Namespace of EIPs and bandwidths: SYS.VPC

Monitoring Metrics

Table 11-1 Metrics of EIPs and bandwidths

ID	Name	Description	Value Range	Monitored Object	Monitoring Interval (Raw Data)
upstream_bandwidth	Outbound Bandwidth	Network rate of outbound traffic (Previously called "Upstream Bandwidth") Unit: bit/s	≥ 0 bit/s	Bandwidth or EIP	1 minute

ID	Name	Description	Value Range	Monitored Object	Monitoring Interval (Raw Data)
downstream_bandwidth	Inbound Bandwidth	Network rate of inbound traffic (Previously called "Downstream Bandwidth") Unit: bit/s	≥ 0 bit/s	Bandwidth or EIP	1 minute
upstream_bandwidth_usage	Outbound Bandwidth Usage	Usage of outbound bandwidth in the unit of percent. Outbound bandwidth usage = Outbound bandwidth/ Purchased bandwidth	0% to 100%	Bandwidth or EIP	1 minute
upstream	Outbound Traffic	Network traffic going out of the cloud platform (Previously called "Upstream Traffic") Unit: byte	≥ 0 Bytes	Bandwidth or EIP	1 minute
downstream	Inbound Traffic	Network traffic going into the cloud platform (Previously called "Downstream Traffic") Unit: byte	≥ 0 Bytes	Bandwidth or EIP	1 minute

 **NOTE**

If a bandwidth is increased or decreased, there is a delay of 5 to 10 minutes for the monitoring metrics to update for the new bandwidth.

Dimensions

Key	Value
publicip_id	EIP ID
bandwidth_id	Bandwidth ID

If a monitored object has multiple dimensions, all dimensions are mandatory when you use APIs to query the metrics.

- Query a monitoring metric:
dim.0=bandwidth_id,530cd6b0-86d7-4818-837f-935f6a27414d&dim.1=publicip_id,3773b058-5b4f-4366-9035-9bbd9964714a
- Query monitoring metrics in batches:
"dimensions": [
 {
 "name": "bandwidth_id",
 "value": "530cd6b0-86d7-4818-837f-935f6a27414d"
 },
 {
 "name": "publicip_id",
 "value": "3773b058-5b4f-4366-9035-9bbd9964714a"
 }
],



11.2 Viewing Metrics

Scenarios

You can view the bandwidth and EIP usage.

You can view the inbound bandwidth, outbound bandwidth, inbound bandwidth usage, outbound bandwidth usage, inbound traffic, and outbound traffic in a specified period.

Procedure

1. Log in to the management console.
2. Click  in the upper left corner and select the desired region and project.
3. In the upper left corner of the page, click  to open the service list and choose **Management & Governance > Cloud Eye**.
4. Click **Cloud Service Monitoring** on the left of the page, and choose **Elastic IP and Bandwidth**.



5. Locate the target metric and click **View Metric** in the **Operation** column to check detailed information.

11.3 Creating an Alarm Rule

Scenarios

You can configure alarm rules to customize the monitored objects and notification policies. You can learn your resource statuses at any time.

Procedure

1. Log in to the management console.
2. Click  in the upper left corner and select the desired region and project.
3. In the upper left corner of the page, click  to open the service list and choose **Management & Governance > Cloud Eye**.
4. In the left navigation pane on the left, choose **Alarm Management > Alarm Rules**.
5. On the **Alarm Rules** page, click **Create Alarm Rule** and set required parameters, or modify an existing alarm rule.
6. After the parameters are set, click **Create**.

After the alarm rule is created, the system automatically notifies you if an alarm is triggered for the VPC service.

NOTE


For more information about alarm rules, see [Cloud Eye User Guide](#).

11.4 Exporting Monitoring Data

Scenarios

If you want to collect EIP traffic statistics within a specified period or analyze the bandwidth or traffic usage of EIPs to locate faults, you can export EIP monitoring data.

Procedure

1. Log in to the management console.
2. Click  in the upper left corner and select the desired region and project.
3. Hover on the upper left corner to display **Service List** and choose **Management & Governance > Cloud Eye**.
4. In the navigation pane on the left, choose **Cloud Service Monitoring > Elastic IP and Bandwidth**.
5. On the **Cloud Service Monitoring** page, click **Export Data**.
6. Configure the time range, period, resource type, dimension, monitored object, and metric.

7. Click **Export**.

 **NOTE**

You can export data for multiple metrics at a time to a CSV file.

- The first row in the exported CSV file displays the username, region, service, instance name, instance ID, metric name, metric data, time, and timestamp. You can view historical monitoring data.
- To convert the time using a Unix timestamp to the time of the target time zone, perform the following steps:
 - a. Use Excel to open a .csv file.
 - b. Use the following formula to convert the time:
$$\text{Target time} = [\text{Unix timestamp}/1000 + (\text{Target time zone}) \times 3600]/86400 + 70 \times 365 + 19$$
 - c. Set cell format to **Date**.

To convert a Unix timestamp of 1475918112000 to Shanghai time (UTC+8), using the following formula:

$$\text{Target time} = [1475918112000/1000 + (+8) \times 3600]/86400 + 70 \times 365 + 19$$

Set the cell format to date and select a presentation format such as 2016/3/14 13:30. Then, the target time obtained will be presented as 2016/10/8 17:15.